


# Imitor

Adjustable multitap delay with up to 32 taps and a unique feedback processing structure. Create rhythmic delays, customizable comb filters, shimmering atmospheres, and more!



# Welcome to Imitor.

Imitor is a delay designed for customization and experimentation. Many multitap delays can be intimidating, with their complicated and cumbersome interfaces, so we designed lmitor with powerful user-friendly controls and tap displays that are fun to interact with, all of which are fully automatable. Set the pre-delay, pan your taps, warp time, crescendo or decrescendo – the delay section of lmitor has so many options at your fingertips.

Play with the Tap Delay modulation section for a wide range of control: adjust modulation, relative LFO phase, speed, and stereo effect. Finally, the Processing section adds a bit of Noise Engineering flavor. Crank Regen to 11, Shimmer your sound, add some suboctaves with Doom, filter your delay with Tone, play with stereo width, or add some not-so-subtle wavefolding.

Imitor excels at long, evolving echoes and creating rhythms from a single sound, but it can also be set to extremely short delay times for comb filtering, flanging, chorus, and more.

Imitor is a delay and echo playground: if you can imagine it, you can create it with Imitor.

Installation	l
Windows	ı
Mac	ŀ
Uninstallation	l
Shortcuts	2
Getting Started	3
Clocked echoes	3
Multitap Rhythms	4
Choruses, phasers, and flangers	5
Tone Page	Ь
Tap Structure	7
Tap Delay LFO	9
Processing	10
Presets	11
Modulation	13
Types of modulation	13
Modulation Assignment	14
Modulation Page	16
LFO 1-4	16
Type: Wave	17
Type: Step	19
Macro	51
Env	55
Clear	23
Modulated parameters column	24
Config Page	56
Controls	56
Help	27
Plugin Locations	28
About NE	29
Special Thanks	29

# Installation

## Windows

Log into portal.noiseengineering.us

Navigate to the "Plugins" tab, and click the link that says "Click here to download the installer for NE Products (W64)"

Double-click the downloaded file to run it.

NE Products will use your web browser to authenticate your plugins. Log into your Portal account on the webpage that opens if prompted, then return to NE Products.

Click on "Update plugins for [email]".

Close NE Products, run your DAW, and your plugins will appear!

## Mac

Log into portal.noiseengineering.us

Navigate to the "Plugins" tab, and click the link that says "Click here to download the installer for NE Products (OSX)"

When the download completes, open the installer file and follow the instructions.

Open NE Products. On Mac, it can be found with Finder in Applications or with Spotlight.

NE Products will use your web browser to authenticate your plugins when you run it. Log into your Portal account on the webpage that opens if prompted, then return to NE Products.

Click on "Update plugins for [email]".

Once plugins are installed, the message at the top of the screen will display "Your plugins are up to date."

Close NE Products, run your DAW, and your plugins will appear!

## Uninstallation

Run NE Products again, and click "Uninstall Plugins."

If you'd like to also remove their preset files, click "Uninstall Plugins and Presets."

Doing this removes all presets in the factory directories, **including user-created presets**, so please copy any files you'd like to save to a different location before performing this action.

# Shortcuts

### Cmd/Ctrl+Click or Cmd/Ctrl+Mouse wheel

For finer control, hold Cmd (Mac) or Ctrl (PC) while moving a parameter.

## **Double click**

Resets any parameter to its default state.

### Scroll

Hover over any parameter and scroll to adjust. Scroll+Cmd (Mac) or Scroll+Ctrl (PC) give finer control.

All of these work to edit step levels in LFO Step shape as well.

# Getting Started

Imitor includes a library of presets that cover some of our favorite Imitor patches and are great starting points for exploring what Imitor can do. In this section, we'll go through a few basic configurations and explore some of Imitor's parameters in use.

To load a preset, click load at the bottom left of the plugin, navigate through the subfolders to find the one you'd like to load, then select it and click Open. You can also use the Category and Preset arrows below the load button to scroll through the preset library.

## Clocked echoes


Load up the classic dotted 8th preset in the Bread And Butter category.



The Blend and Regen parameters (outlined in pink) will change the volume of the delay and number of echoes respectively. The Beats setting (outlined in yellow) will change the echo timing: by default, this preset plays dotted 8th notes, but by adjusting this number that timing can be changed. For example, changing the fraction to 2/1 will give 8th note echoes, and 1/1 will give quarter notes.

# Multitap Rhythms

Load up the tippity preset in the Pudding category.




This preset uses the multitap structure of lmitor to create rhythmic patterns in its echoes. Multitap delays have different points in their delay line that can be monitored, creating echoes even when feedback (the Regen parameter) is set to 0. Imitor has a number of ways to adjust tap timing, panning, and behavior.

Try running a single pluck or drum hit through this preset and listen to the pattern that is created, then adjust that pattern with the Tap Total parameter and Tap checkboxes (outlined in yellow). Tap Total adjusts the number of audible taps, and the checkboxes enable or disable taps.

The Index parameter (outlined in pink) adjusts tap modulation: when Index is turned up an LFO is sent to the delay taps, and you'll hear some pitch warbling as the echoes play. This can be disabled by turning Index down, and can be further adjusted by changing the settings of the parameters in the Tap Delay LFO column.

# Choruses, phasers, and flangers

Load up the chorus preset in the Bread And Butter category.



Imitor's delay time can be extremely fast, which is perfect for creating effects like choruses, phasers, and flangers. This preset uses a low Time setting and LFO modulation to create a wide chorus. The timbre of the chorus can be adjusted with the Time parameter (outlined in yellow), and the rate and depth of modulation can be adjusted with the Speed and Index controls (outlined in pink) respectively.

Short delay times with no modulation can also be used to create resonant effects that sound almost acoustic. Try out the karp preset in the Bread And Butter category with short sounds like drums or noise bursts for some wild results.

# Tone Page



#### Volume In

Controls the level of sound coming into the plugin.


### **Blend**

Controls the dry/wet balance. Fully left, the unmodified input signal is passed through. Fully right, only the processed signal is heard. Points in the middle give you a mix of both.

#### **Volume Out**

Sets the output level of the plugin.

# Tap Structure



## **Tap Total**

Sets the number of taps. With regen at minimum, this will be the number of echos heard.

## **Tempo Sync**

When unchecked, Imitor's delay time is unsynced. When checked, Imitor's delays are synced with the DAW tempo and meter.

### **Time** (Tempo Sync disabled)

Sets the amount of time between taps in seconds. At low settings echoes occur at audio rates, useful for effects like comb filtering and flanging.

#### **Beats** (Tempo Sync enabled)

Sets the amount of time between taps in seconds; divisions/multiplications are presented as a fraction. For example, a 16th note delay would be set with 4/1.

#### \*2 /2 (Beats, Tempo Sync enabled)

Doubles/halves the delay time.

#### Pre Delay

Sets the amount of time between an input sound and the first delay tap. Pre delay time presented as a fraction of the Time or Beats setting. For example, a predelay twice the length of the delay time would be set with ½.

### \*2 /2 (Pre Delay)

Doubles/halves the pre-delay time.

### **Time Warp**

Bipolar; warps the tap timing to start slow and speed up right of center, or start fast and slow down left of center. Tap spacing is even when control is centered. Note that this parameter only affects tap timing when Tap Total is set to 3 or greater.

### **Decay**

Bipolar; changes whether the taps crescendo to the left, have equal level in the center, or decrescendo to the right.

### **Angle**

Bipolar; adjusts tap panning. This parameter works in conjunction with the Rotate parameter: Angle sets the panning of the first tap, and Rotate offsets the pan of the following taps.


#### Rotate

Bipolar; offsets tap panning based on position of Angle.

### **Tap** (1-32 checkboxes)

Tap enable/disable checkboxes. Taps are muted when unchecked. Useful for creating rhythmic delays.

# Tap Delay LFO



#### Index

Sets the amount of LFO modulation sent to the taps.

#### Dance

Changes the relative phase of the LFOs used to modulate the timing of each tap.

#### Speed

Sets the speed of the LFO.

#### Stereo

When set to the left, the LFOs modulate left and right taps equally. As this parameter is increased, left and right tap modulation is decoupled, creating a wider stereo sound.

# Processing



## Regen

Sets the feedback amount. Goes well above 100%.

#### Shimmer

Adds a one-octave pitch shift to the feedback loop. Only audible when Regen is above 0%.

#### Doom

Adds a chaotic suboctave shift to the feedback loop. Only audible when Regen is above 0%.

#### Tone

Bipolar; controls the filter in the feedback loop. Functions as a lowpass filter to the left and highpass filter to the right. Filter is bypassed in the center.

#### Tone Q

Resonance level for the Tone filter.

#### Width

At left, the feedback loop is mono. Stereo width is increased as the slider is moved to the right.

#### Crunch

A not-so-subtle wavefolding effect at the end of the delay signal chain.

# Presets



Presets are stored in the computer's file system, and the controls below allow for modification and navigation through the files and folders of presets. You can create a new preset "Category" by creating a subfolder in the preset directory, and saving new presets within it.

#### load

Load a preset.

#### save

Save a new preset.

### < > (category)

Loads the next/previous folder of presets in the preset directory.

#### < > (preset)

Loads the next/previous preset.

#### nudae

Applies a small amount of randomization all tonal parameters and modes. Randomization can be bypassed per control in their individual modulation menus. Useful for creating slight variations of sounds.

#### rand

Completely randomizes all tonal parameters and modes. Randomization can be bypassed per control in their individual modulation menus. Use this to create inspiring new sounds and ideas.

### reset

Resets all parameters to their default settings.

## **Disable View**

Hides the tap display; can improve CPU performance when GUI is open.

## shhh

Panic button; ends all notes.

# Modulation

All plugins feature a comprehensive routing system making use of a variety of modulation types and sources. When modulation is enabled on a parameter, a box showing the range of enabled modulation will appear, and a small indicator will move within the range box showing the exact position of the modulation.



# Types of modulation

Parameters can be modulated from a variety of sources:

#### **LFOs**

Four onboard LFOs that offer a variety of modes, from simple waveforms to step sequencers. More detail on LFO modes can be found in the section below titled "Modulation page."

#### **Macros**

Four macro sliders can be assigned to any number of parameters. The macros can in turn be mapped to MIDI controllers, automated, or modulated with other LFOs.

#### Env


Envelope follower. Turns the dynamics of the incoming signal into a modulation source.

#### MIDI CC

Parameters can be assigned to MIDI CCs. If a parameter is assigned, the CC number will appear here. (Note: MIDI mapping is not supported in all DAWs.)

# Modulation Assignment

When a parameter is right-clicked (Control+click on Mac), a context menu appears with modulation routing options:



#### Parameter slider

A copy of the parameter being modulated, for easy adjustment.

#### On

Each modulation source has a checkbox; when checked, modulation from that source is enabled.

#### Index

Sets the amount of modulation from a particular source. Fully left, modulation is bypassed.

#### Dir

Direction. Sets the polarity and inversion of incoming modulation.

- --> unipolar: modulates from the point selected on the parameter up to the level indicated by the Index setting
  - <-> bipolar: modulates around the center point set by the parameter
  - -- inverted unipolar: opposite modulation from unipolar
  - >-< inverted bipolar: opposite modulation from bipolar

#### Curve

Each modulation source has a Curve slider that changes how modulation affects the parameter. In the center, modulation is linear, and the parameter movement matches incoming modulation exactly. To the right modulation is more logarithmic, and to the left more exponential.

#### **Allow Randomize**

When checked, this parameter can be randomized when "rand" (Tone page) is clicked.


#### Learn CC

Click this to enable MIDI CC learn on a parameter. Move a parameter on your MIDI controller and the plugin will exit learn mode and the parameter will now respond to that CC. If clicked by mistake, click "waiting on CC" to exit learn mode. Click "forget CC" to remove an assignment.

**Clear modulation** (only visible when MIDI Learn is checked on the Config > Controls page) Resets modulation checkboxes, amounts, direction, and curve. Does not affect CC assignments.

# Modulation Page

Click the sections in the left column to navigate to that page and edit modulator settings and routings.



# LFO 1-4

#### Index

Sets the modulation range of the LFO.


#### **Type**

Sets the type of LFO. Options include Wave, Step, and ADR, described in detail in the sections below.

#### **Reset LFO**

Resets the LFO back to its default state, respecting Type.

# Type: Wave



### Sync

Sets the source of timing for the modulator.

- Free: A single completely freerunning LFO; never resets.
- Transport: Speed is set in seconds, but the LFO follows the transport of the DAW.
- Tempo: A single LFO that is synced to the DAW's tempo and transport.

#### Speed/Beats

Sets the rate of the LFO. In unsynced modes, this is a slider that sets the rate in seconds. In synced modes (Tempo and Poly Tempo), this is a fraction that sets the rate in beats (for example, 4/1 would be equal to 1 bar in 4/4 meter). If a synced mode is selected, the rate can be doubled or halved with the \*2 and /2 buttons respectively.

#### Shape

Morphs between different waveforms.

#### saw/sin/tri/sqr/was

Selects a shape preset for the waveform. Choose saw, sine, triangle, square, or inverted saw.

#### **Phase**

Changes the starting point of the wave.

### 0/90/180/270

Selects a preset for the phase of the waveform.

## Time Warp

Skews the timing of the waveform.


#### Noise

Adds randomness to the waveform.

**Color** (only visible when Noise is above minimum)

Changes the intensity of randomness added to the waveform.

# Type: Step



### Sync

Sets the source of timing for the modulator.

- Free: A single completely freerunning LFO; never resets.
- Transport: Speed is set in seconds, but the LFO follows the DAW's transport.
- **Tempo:** A single LFO that is synced to the DAW's tempo and transport.

#### Loop

Repeats infinitely when checked, or plays once when unchecked.

### Speed/Beats

Sets the rate of the sequencer. In unsynced modes, this is a slider that sets the rate in seconds. In synced modes, this is a fraction that sets the rate in beats (for example, 4/1 would be equal to 1 bar in 4/4 meter). If a synced mode is selected, the rate can be doubled or halved with the \*2 and /2 buttons respectively.

#### Count

Sets the steps in the sequencer; the up and down arrows change the count by one, and the \*2 and /2 buttons respectively double or halve the count.

#### Smooth

Adjusts how smooth the transition between steps is.

### **Time Warp**

Skews the timing of the sequencer.

#### Random

Adds per-step randomization to the sequence.

### Graph

Edit your sequence here by clicking and dragging or use the preset buttons:

- rand: Randomizes the sequence entirely.
- nudg: Slightly changes the values of each step.
- up: Generates an ascending pattern across the steps.
- dn: Generates a descending pattern across the steps.
- ud: Creates a triangle pattern across the steps.
- du: Creates an inverted triangle pattern across the steps.

# Macro



Mac 1-4

Four sliders that can be assigned to any number of other parameters, and modulated by LFOs or MIDI CCs.

# Env



## **Envelope**

An indicator of the current Envelope modulator value.

## Index

Sets the range of the Envelope modulator.

# Clear

This page is home to the "Clear All" button. Clicking this removes all modulation routings from the patch. Use it wisely.



# Modulated parameters column

When a modulator (LFO, Macro, or Other) is assigned to a parameter, the parameter will appear in this list when on that modulator's page. For instance, if LFO 1 is modulating Attack, click LFO 1 on the left side to view the modulation amount, curve, and checkbox for Attack (and any other LFO 1 modulated parameters) on the right.



#### Group

Selects a category of parameters, grouped by location in the interface. For example, the Fold parameter is in the Oscillator group.

#### Param

Selects a parameter from the current Group category.

#### Add Route

Adds modulation routing for the selected parameter from the selected modulator.

#### **CIr Routes**

Click twice to remove all modulation assignments for the current modulator. To remove a single assignment simply uncheck the On box.

#### **Add Rand**

Adds a random modulation destination.

#### On

Each modulation source has a checkbox; when checked, modulation from that source is enabled. When unchecked on this page, it is removed.

#### Index

Sets the amount of modulation from a particular source. Fully left, modulation is bypassed.

#### Dir


Direction. Sets the polarity and inversion of incoming modulation:

- --> unipolar; modulates from the point selected on the parameter up to the level indicated by the Index setting
  - <-> bipolar; modulates around the center point set by the parameter
  - <-- inverted unipolar; opposite modulation from unipolar
  - >-< inverted bipolar; opposite modulation from bipolar

#### Curve

Each modulation source has a Curve slider that changes how modulation affects the parameter. In the center, modulation is linear, and the parameter movement matches incoming modulation exactly. To the right modulation is more logarithmic, and to the left more exponential.

# Config Page



# Controls

#### MIDI Learn

Enables internal MIDI learn for most parameters.

# Graphics

### **Static**

Adds some retro flare to the GUI.

#### Size

Sets the size of the plugin window.

#### Hue

Sets the color scheme of the plugin.

#### Fire

Adds some attitude to the plugin GUI.

# Help

## **Tooltips**

Turn tooltips on or off.

#### **Get Manual**

Opens the plugin product page.

## I Need Help

Uploads anonymized system information used for troubleshooting and opens the support form. If you're having an issue please press this button and fill out the form to tell us what the problem is! You can also always reach us at <a href="noiseengineering.us/pages/contact">noiseengineering.us/pages/contact</a>. Drop us a line and we'll get back to you within two business days.

## See All NE Plugins

Opens the plugin shop. Check out all the Noise!

# Plugin Locations

Plugin presets install to:

**Windows:** C:\Users\Public\Documents\Noise Engineering\

Mac: /Users/[name]/Library/Audio/Presets/Noise Engineering/

Noise Engineering plugins are installed to the default locations for the specified plugin formats. In a majority of cases, plugins will not need to be moved. In the rare instance that you need to move your VST plugins, find them in the following locations.

Windows: C:/Program Files/Common Files/VST3/Noise Engineering/

Mac: /Library/Audio/Plug-Ins/VST3/

Note that AU and AAX plugins cannot be moved. For reference, they are installed here:

Mac AU: /Library/Audio/Plug-Ins/Components/

Mac AAX: /Library/Application Support/Avid/Audio/Plug-Ins/Noise Engineering/

Windows AAX: C:/Program Files/Common Files/Avid/Audio/Plug-Ins/Noise Engineering/

# About NE

Noise Engineering is located in Los Angeles, California. We started around 2014 when Chief Noisemaker Stephen McCaul wanted a hobby for his off time from his day job and started making Eurorack modules in a spare bedroom at home. One thing led to another and a couple of years later, he and wife Kris Kaiser quit their day jobs and took the company full time. Noise Engineering has since grown in size and has established itself as a well-regarded and innovative synthesizer brand, with products in Eurorack, 5U, and multiple software platforms.

# Special Thanks

Starthief Kerry Leva

Dave Dean Matt Lange

Douglas Hill Rene Boscio

Hans Besselink Shanda Nunez

James tobias Broken Circuits

Josh Sager Yugo Oshima