



HopTech
6398 Dougherty Rd Ste 18
Dublin, CA 94568

www.hoptech.com
1-925-875-0246
Fax: 1-925-875-0248

Octoberfest/Marzen Kit Instructions

Ingredients:

6 lbs Pale Liquid Malt Extract
.5 lb 95° Crystal Malt, 1 lb DWC Carapils Malt - crushed and packed together
1.5 lb Munich Malt, .5 lb Vienna Malt - crushed together and packed separately
Tettnanger Hops in a multi-pack marked "Bock" (not a misprint)
(weight varies according to alpha acid/oil content)
Irish Moss pre-mixed in the package with bittering hops
Wyeast 1338XL liquid yeast (if made as an ale) or Wyeast 2206XL (if made as a lager)
3/4 Cup Corn Sugar for priming

Specifications: This kit makes an Octoberfest/Marzen style beer. It can be made as an ale or a lager depending on the yeast selected. It has an OG about 1.060 about 18 IBUs of bitterness. It will typically contain around 6% alcohol by volume.

Important: If you're not planning to brew right away, it is best to store this kit in the refrigerator, and if your brew date is potentially a month or more away, take out the hops package and store that in the freezer (but don't freeze anything else in the kit). If you keep the kit in the refrigerator, warm the malt extract bucket in a sink of hot water before use to make it easier to pour.

Instructions:

These instructions assume you are doing a partial boil of approximately 3 gallons in a 5 gallon pot and then adding water after cooling to bring the volume up to 5 gallons. If you are doing a full 5 gallon boil, start with about 6 gallons of water and you shouldn't have to add any later.

Partial Mash: The Munich and Vienna Malts included with this kit need to be mashed - they have been packed separately from the other grains. Do this by bringing 2.5 quarts of water to 170°F in a 4 qt. saucepan - the thicker the saucepan the better. Anodized or coated aluminum is fine, but not plain aluminum. Remove the pan from the heat and thoroughly stir in *only* the Munich/Vienna Malts (save the other grains for later!). Cover and let sit for ½ hour.

Now put 2.5 to 3 gallons of water in your boiling kettle (to speed up the boiling time, you can use hot water). Over a bowl, scoop the mashed grains into a grain steeping bag. Add the remaining package of grains to the bag. Tie it loosely at the top making sure the grains have plenty of free space around them. Put the grain bag into the water as you start to heat the water, adding any liquid you caught in the bowl or left in the saucepan into the water. When the water reaches 180°F, remove the grain bag but let all the water drain from the grains back into the kettle. You may want to dip the grain bag several times as if it were a teabag as the water comes up to temperature and again right before you remove it. When the water comes to the boil turn off the heat and add all of the malt extract (if you have an electric stove, take the pot off the burner). To help get all of the malt extract out of the bucket, dip the bucket in the water and swirl it around to dissolve the extract, repeating until you get it all. Stir the extract in well, making sure it is all dissolved and there is none on the bottom of the pot before you turn the heat back on. Bring the liquid to the boil. Once it starts boiling, turn off the burner (or remove the pot) and add the

bittering hops. These are the hops in the section of the package marked “B” (for bittering). There is also Irish Moss in with these hops to help the proteins coagulate. The reason we turn off the heat is that when adding the hops there is a tendency for the kettle to boil over and removing the heat prevents this. Turn the heat back on. When the kettle starts to boil again, start timing 60 minutes. (In the initial stages of the boil, the kettle is most vulnerable to boiling over so pay close attention. Also, the initial foaming tends to leave hop particles on the sides of the kettle. Using your brew spoon, wash these particles back into the liquid.)

5 minutes before the end of the boil, remove the kettle from the heat and add the aroma hops. They are in the section of the foil bag marked “A” (for aroma). Stir them in well, then reapply the heat, boiling for the remaining five minutes. (The heat is removed to prevent a boil-over.)

Cover the kettle and chill the wort. Usually this is done by putting the kettle in a sink full of ice water. You may have to replace the ice at least once. It also helps to swirl the kettle’s contents to make it cool faster, but do not remove the lid to stir.

If you have a settling tank, pour the wort into the settling tank. Add cold, sterile water to bring the level up to about 5 gallons and let the wort settle. If your settling tank has a spigot, let the wort settle until the level of the trub is below the spigot. If it never gets that low after 3 hours, then go ahead and transfer the wort anyway. The little bit of sediment that you’ll get won’t matter that much. If at the end of the transfer you start to pick up more sediment, shut the spigot off as soon as possible. This is the sediment we really want to avoid in our fermenter.

This kit contains liquid yeast, so you must pop the packet 6 to 12 hours prior to brewing, following the directions on the packet.

Transfer the wort to your fermenting tank, aerating it as much as possible by “fanning” the wort down the sides of the container. Pitch the yeast and stir well to mix and aerate the wort. Put the lid on the fermenter and attach the airlock.

If you are making this kit as an ale (with Wyeast 1338) the fermentation can be done at room temperature. If you are making this kit as a lager (with Wyeast 2206), start your fermentation at 65°F, then once it is going strong, drop the temperature to 48-58°F until fermentation is complete. Then lager for at least two weeks at 35°F.

Once the wort has fermented and cleared (usually about 2 weeks for ales, or after the lagering period for lagers), transfer to a bottling bucket leaving as much sediment behind as possible and trying to minimize the amount of air pickup by doing a gentle transfer. Boil about a pint of water and add the priming sugar stirring until it is dissolved. (This kit includes 3/4 cup of priming sugar which will provide a normal amount of carbonation. If you like your beer a little less carbonated, use only 1/2 cup.) Pour the liquid into the bottling bucket (there is no need to cool it) and stir thoroughly but gently. Bottle and cap the beer.

Leave the beer at room temperature for three days to a week and then place in the refrigerator for a few days to allow the CO₂ to get fully dissolved in the beer. Now drink and enjoy!

Questions or problems? Give us a call on our advice line: 925-875-0246. Hours: Monday through Friday 10am to 5pm Pacific Time. Also find useful advice at www.hoptech.com