

City of Bend Fire & Rescue

Section 1.7 - Wildland

Task 1.7.2 Deploying wildland progressive hose lay - 2 Person

STANDARD:

1. Properly deploy attack line from Pondosa Pack.
2. Extinguish fire flank as hose is deployed
3. Use all safety precautions.

RESOURCES:

1. Full wildland protective clothing and safety gear
2. One engine with Pondosa Packs

PROCEDURE:

1) Deploy progressive hose lay and attack fire along flank.

- a) Both crew members remove Pondosa Packs from compartment and place on
- b) Back. Second person removes hose clamp from compartment and places in pocket.
- c) Deploy a 100' roll of 1.5" and connects to discharge.
- d) Nozzle-man attaches nozzle to initial line and signals for water. Then advances line to anchor point and along flank while extinguishing fire.
- e) At the end of the initial line the second person places clamp on hose, then removes first section of hose from the nozzle-mans pack and unrolls it back along the fire line. Placing the male coupling on the nozzle-mans shoulder
- f) The nozzle-man removes nozzle from hose and attaches it to the new section while the second person connects the sections of hose together.
- g) The second person releases hose clamp when nozzle-man calls for "water"
- h) Continue to advance along the flank.
- i) Repeat steps 4 through 7 and leave 1' lateral line at "T".
- j) Rotate positions and continue evolution.

2) Deploy lateral lines at "T"

- a) Connect lateral at "T" and open valve for use as personnel are available.

Safety Considerations:

1. Ensure LCES is in place
2. Establish a solid anchor point
3. Do not advance hose line until water is flowing
4. When possible, work from the black
5. Always maintain situational awareness