




MANOS DEL URUGUAY

## Fácil Shawl

by Lisa R. Myers



**FINISHED SIZE**

68" from wingtip to wingtip

18" deep at center spine

**MATERIALS**

Manos del Uruguay CLARA (100% superwash merino, approx. 100g/385 yds), 1 sk. Shown in C23 Velvet.

US 7/4.5mm needle, 24" circular or longer; or size to obtain gauge  
4 stitch markers

**GAUGE**

20 sts and 28 rows = 4" before blocking

15 sts and 22 rows = 4" after blocking

**ABBREVIATIONS**

k: knit

k2tog: knit 2 stitches together

m: marker

ndl(s): needle(s)

p: purl

pm: place marker

rep: repeat

RS: right side

slm: slip marker

st(s): stitch(es)

yo: yarnover

**INSTRUCTIONS**

Cast on 4 sts.

Row 1 (RS): K2, yo, k2. 5 sts.

Row 2: K2, yo, p1, yo, k2. 7 sts.

Row 3: K2, (yo, k1) 3 times, yo, k2. 11 sts.

Row 4: K2, pm, yo, p2, pm, p3, pm, p2, yo, pm, k2. 13 sts.

Row 5: K2, slm, yo, k to next m, slm, yo, k to next m, yo, slm, k to last m, yo, slm, k2.

Row 6: K2, slm, yo, p to last m, yo, slm, k2.

Rep previous 2 rows 5 times more. 49 sts, 15 between the center markers and 17 at each side.

*Note: The difference between the previous 2 rows and the next 2 rows is in which yarnovers come before the markers and which come after. Read carefully to keep your eyelets properly aligned.*

Next row: K2, slm, yo, k to next m, yo, slm, k to next m, slm, yo, k to next m, yo, slm, k2.

Next row: K2, slm, yo, p to last m, yo, slm, k2.

Rep previous 2 rows 3 times more. 73 sts, 15 between center markers and 29 at each side.

Next row: K2, slm, yo, k to next m, yo, slm, k to next m, slm, yo, k to next m, yo, slm, k2.

Next row: K2, slm, p to last m, slm, k2.

Rep previous 2 rows until center spine measures 14½", ending with a wrong-side row.

Next row: K2, sm, yo, (k2tog, yo) to 1 st before m, k1, yo, slm, (k2tog, yo) to 1 st before next m, k1, yo, slm, k1, (yo, k2tog) to last m, yo, sm, k2.

Knit 3 rows without any yarnovers. Bind off knitwise.

**Finishing**

Weave in ends. Soak scarf in lukewarm water (with woolwash if desired) for 15-20 minutes. Drain, then wrap in towel and squeeze out excess water. Pin out to finished measurements and allow to dry.