



July's Beer Kit of the Month...

Single Hop Wallaby Saison



⚠ If your kit has **liquid yeast**, put it in the refrigerator as soon as possible.

Now that we've reached the zenith of summer it would only be right to brew one of the more refreshing and distinctive of beer styles. The Wallaby is a continuously hopped (albeit 2 ozs.) Saison featuring citrusy and floral Australian Galaxy hops. Yeast selection and fermentation temp. will affect the flavor this recipe considerably. Both the Wyeast 3711 and White Labs 566 are recommended in the 70-85F range.

Here are the relevant stats for this delicious brew...

O.G.: 1.051 F.G.: 1.010 ABV: 5.4% IBU: 38 SRM: 3

Kit Ingredients


- Specialty Steeping Grains:
 - 8 oz. Goldpils Vienna
- 1 lb corn sugar
- 3.3 lb wheat malt extract
- 3.3 lb pilsen malt extract
- 2 oz Australian Galaxy (30,20,10,5, 0 MIN. boil additions)
- 1 cup corn sugar (for bottling)
- Muslin sack to steep grains
- Belle Saison, Wyeast 3711, WLP566, or OYL-500 yeast

⚠ Please make sure that the kit contains these items. Call us at 608-257-0099 before brewing if any item is missing. Thanks!

Directions

Sanitize everything well! Remember to stir periodically throughout the boil!

0. If you are using liquid yeast, about three to six hours before you are going to brew, remove the liquid yeast from the refrigerator. If it is a Wyeast pack, break the nutrient pack inside the yeast package according to the directions on the package. Leave the yeast out at room temperature until it is time to pitch your yeast into your beer.
1. Fill your kettle with 10 quarts of cold water, pour the crushed **steeping grain** into the grain sack, tie the sack closed, and place it into your kettle (**Note:** If your brew system allows you to boil more than 10 quarts, feel free to boil more liquid. This will allow you to get a bit better utilization from your hops and reduce caramelization). Turn on heat and bring mixture to 160F and then turn off heat. Steep the grains for 10 minutes. Do **not boil** grains.
2. While your grains are steeping, heat 2 quarts of water to 170F in a separate pot. After the 10 minute steep, remove grains from the mixture and rinse (sparge) them with the 2 quarts of hot water, collecting the runnings in your boil kettle. Then turn on the heat and bring the mixture to a boil. You will be boiling the mixture, called wort, for a total of 30 minutes. However, keep reading, because you'll be adding hops during that time.



3. When you achieve a boil, turn off the heat and empty the **Pilsen malt extract** into the hot water. (Extract may pour more easily if you open the top of the container and place it in a saucepan of hot, not boiling, water for ten minutes prior to pouring. Do not apply direct heat to the jar). Stir extract into wort well.
4. Turn the heat back on and bring the wort to a boil. Upon initial boil the wort may foam up (called a “hot break”). If this happens, reduce the heat until the foam recedes, then turn up the heat, bring back to a boil, and maintain a rolling boil. Start your 30 minute boil timer now. Add **1/2 oz of Galaxy** hop pellets and boil the wort for 10 minutes. (If you want a beer with milder bitterness, only add 1/4 oz of Galaxy hop pellets here.)
5. After these 10 minutes it’s time for another hop addition. Turn off the heat and add the **3.3 lb wheat malt extract** and **1/4 oz Galaxy** hop pellets. Turn the heat back on and continue to boil for 10 more minutes.
6. After these 10 minutes (20 minutes total) add **¼ oz. Galaxy**. After 5 more minutes (25 total) add **½ oz Galaxy**. After 5 additional minutes (30 total) turn off the heat and add the last **1/2 oz Galaxy** and **1 lb. corn sugar**. (Optional: Instead, add the **1 lb. corn sugar** to the primary fermentor 4 - 5 days into fermentation. To do so, dissolve the corn sugar in about a pint of boiling water, chill the sugar solution to room temp, and pour into fermentor.)
7. Sanitize fermentor, stopper, and air lock with sanitizing material according to its directions.
8. Fill the sanitized fermentor with 2.5 gallons of cold water (use less if you boiled more water than the recipe calls for). Cool your hot wort down to around 110-120F by placing your pot carefully into a sink of ice water for 15-30 minutes or by using a wort chiller. Carefully pour the hot wort into the cold water in the fermentor. If necessary, top up to 5 gallons with cold water.
9. Take a temperature reading of the wort. If the wort mixture in the fermentor is below 80°F (not warm to the touch), give the wort a good shake or a good stir with a sanitized metal or plastic spoon. Here you are trying to aerate the wort, which will help your yeast get going. This is also a good time to take a hydrometer reading. The number from this reading is your starting gravity. Add your beer **yeast**. Instructions are on the yeast package.
10. Seal your fermentor. Attach the fermentation lock half filled with water. Ferment at 70°-95°F for around 14 days. Note that it can take up to 24 hours for active fermentation to be visible. If you don’t see any activity in the air lock or foam on the surface of beer after 24 hours, call us at 608-257-0099. If doing a double stage fermentation, siphon the beer into the glass carboy after 5-7 days in the primary fermentor (the beer may be transferred to the glass carboy as soon as the foam has fallen far enough so the carboy will not overflow).
11. After 14 days, if your beer has ceased fermentation, you can go ahead and bottle or keg your beer. Whether you bottle or keg, sanitize everything that will contact the beer during packaging, including bottles, caps, kegs, siphon tubing, bottle filler, etc. Also, now is a good time to take a hydrometer reading. This would be your beer’s final gravity.
 - a. **Bottling, Single-Stage Fermentor**: Siphon beer into sanitized bottles. Pour just under 1 tsp. corn sugar in each bottle. Cap and turn bottles upside down several times to mix in sugar.
 - b. **Bottling, 2-Stage Fermentor**: Rack the beer carefully off the sediment into a sterilized fermentor or bottling bucket from the carboy. Bring $\frac{3}{4}$ pint of water to a boil. Turn off heat. Dissolve 1 cup of corn sugar in this hot water and stir gently into the beer. Bottle and cap.

- c. **Kegging:** Siphon the beer into your sanitized keg, purge the oxygen from the head-space, hook up to your CO2, wait, and enjoy!
12. Store upright at room temperature (~70F) for 14 days to carbonate. Beer may then be stored at cooler temperatures to age. Beer may be consumed at any time, though it will continue to improve for several weeks.