



WDBC's Future Tense IPA

All-Grain Kit



⚠️ If your kit has **liquid yeast**, put it in the refrigerator as soon as possible.

This West Coast IPA is crystal clear and hopped up with Citra and Nelson Sauvin, leading to notes of kiwi and gooseberry. This is a clone recipe of Working Draft Beer Company's clear IPA. So next time Future Tense is available from Working Draft, head on over and see how your version compares to the original!

Calculated Approximate: O.G.: 1.062 F.G.: 1.016 ABV: 6.1% IBU: 65 SRM: 3

Please Note: This recipe and these instructions assume a 5 gallon batch size with 70% efficiency for a standard homebrewing setup. You may want to tweak the numbers to fit your brewhouse.

The gravity, IBU, and SRM stats are approximations, so don't worry if you are a few points high or low.

Kit Ingredients

- 12lb US Pilsen malt
- 1 oz Chinook hop pellets
- 1 cup corn sugar (for bottling)
- Optional - Isinglass
- 3 oz Citra hop pellets
- Dry yeast S-04, Wyeast 1098, WLP007, Omega Yeast OYL-011
- 4 oz Nelson Sauvin hop pellets

⚠️ Please make sure that your kit contains these items and call us at 608-257-0099 before brewing if any item is missing. Thanks!

Directions

Sanitize everything well! Remember to stir periodically throughout the boil!

0. If you are using liquid yeast, about three to six hours before you are going to brew, remove the liquid yeast from the refrigerator. If it is a Wyeast pack, break the nutrient pack inside the yeast package according to the directions on the package. Leave the yeast out at room temperature until it is time to pitch your yeast into your beer.

You may want to use one of the following methods to help your yeast ferment your yummy beer:

- a. Make a starter. About 2 days before you are going to brew, mix 3.5 oz of dry malt extract in 1 liter of water, boil for 15 minutes, cool down to below 80F, add your **yeast**, and let ferment for 24 hours. If you are not using a stir plate, you may want to swirl your starter a few times a day. After 24 hours, put the starter in the fridge and leave it in there until about 3 hours before you brew. When it is time to add your yeast at the end of the brew day, decant the liquid and add the yeast sludge at the bottom of the starter container.
 - b. Use multiple yeast packs.
1. Fill your kettle with 4.5 gallons of water and heat it to 159F. Pour crushed **grain** into your mash tun, stirring carefully. Check the temperature, make sure it is 148F. If it is too low, add hot water to bring up the temperature. Mash the grains for 90 minutes.

2. While your grains are mashing, heat 4.25 gallons of water to 170F in a separate pot. After the mash, vorlauf (drain 1-2 liters, or until wort is running clear and return this liquid to the mash tun) and drain the liquid from the grain. Then, sparge (rinse) the grains with the 4.25 gallons of hot water, collecting the runnings in your boil kettle. Then turn on the heat and bring the mixture to a boil. You will be boiling the mixture, called wort, for a total of 90 minutes. However, keep reading, because you'll be adding hops during that time.
3. Upon initial boil the wort may foam up (called a "hot break"). If this happens, reduce the heat until the foam recedes, then turn up the heat, bring back to a boil, and maintain a rolling boil. Start your 90 minute timer at this point in the brewing process.
4. After 30 minutes, add **1 oz of Chinook** hop pellets and boil the wort for 60 more minutes. This hop addition will impart most of the bitterness to your beer.
5. After boiling for a total of 90 minutes, you are done boiling your beer, so it's time to turn off the heat. Once you have turned off the heat, add **2 oz Citra** hop pellets and whirlpool for 15 minutes. This means simply stir your wort and cover the kettle for 15 minutes.
6. Sanitize fermentor, stopper, and air lock with sanitizing material according to its directions.
7. After the 15 minute whirlpool, cool your hot wort down to around 70-80F by placing your pot carefully into a sink of ice water or by using a wort chiller. Carefully pour the wort into the fermenter.
8. Take a temperature reading of the wort. If the wort mixture in the fermentor is below 80°F (not warm to the touch), give the wort a good shake or a good stir with a sanitized metal or plastic spoon. Here you are trying to aerate the wort, which will help your yeast get going. This is also a good time to take a hydrometer reading. The number from this reading is your starting gravity. Add your **beer yeast**. Instructions are on the yeast package.
9. Seal your fermentor. Attach the fermentation lock half filled with water. Ferment at 60°-72°F for around 14 days. Note that it can take up to 48 hours for active fermentation to be visible. If you don't see any activity in the air lock or foam on the surface of beer after 48 hours, call us at 608-257-0099. If doing a double stage fermentation, siphon the beer into the glass carboy after 7-10 days in the primary fermentor (the beer may be transferred to the glass carboy as soon as the foam has fallen far enough so the carboy will not overflow).
10. If you are going to clarify with Isinglass, wait to move to the next step until fermentation is complete.
11. However you ferment, add **1oz Citra** and **4oz Nelson Sauvin hop pellets** to your beer after about 7 -10 days of fermentation (if doing two-stage fermentation, add these hops when you siphon your beer into the secondary fermentor). If you are clarifying with Isinglass, add **Isinglass** at this point.
12. Allow the dry hops to stay in contact with the beer for 3-5 days. After 3-5 days, if your beer has ceased fermentation, you can go ahead and bottle or keg your beer.
13. Whether you bottle or keg, sanitize everything that will contact the beer during packaging, including bottles, caps, kegs, siphon tubing, bottle filler, etc. Also, now is a good time to take a hydrometer reading. This would be your beer's final gravity.
 - a. **Bottling, Single-Stage Fermentor:** Siphon beer into sanitized bottles. Pour just under 1 tsp. corn sugar in each bottle. Cap and turn bottles upside down several times to mix in sugar.
 - b. **Bottling, 2-Stage Fermentor:** Rack the beer carefully off the sediment into a sterilized fermentor or bottling bucket from the carboy. Bring $\frac{3}{4}$ pint of water to a boil. Turn off heat. Dissolve **1 cup of corn sugar** in this hot water and stir gently into the beer. Bottle and cap.
 - c. **Kegging:** Siphon the beer into your sanitized keg, purge the oxygen from the head-space, hook up to your CO2, wait, and enjoy!
14. If you bottled, store bottles upright at room temperature (~70F) for 14 days to carbonate. Beer may then be stored at cooler temperatures to age. Beer may be consumed at any time, though it will continue to improve for several weeks.