



# MVP Pale Ale

⚠ If your kit has **liquid yeast**, put it in the refrigerator as soon as possible.

This beer ain't been nothin' but a winner. It's piney, tropical, citrusy hop aroma and biscuity, slightly sweet malt flavor are the best, no contest. And all that during only a 30 minute boil? GIVE IT ALL THE TROPHIES!

**Calculated Approximate: O.G.: 1.048 F.G.: 1.012 ABV: 5.0% IBU: 39 SRM: 6**

## Kit Ingredients

- 3 lb Pale Ale dry malt extract
- 3.3 lb Goldpils Vienna malt extract
- 1 oz Chinook hops (at 30 min)
- 1 oz Amarillo hops (at 0 min)
- 2 oz Mosaic hops (1 oz at 0 min, 1 oz at dry hop)
- 1 cup corn sugar (for bottling)
- Dry Yeast US-05, Wyeast 1056, WLP001

⚠ Please make sure that your kit contains these items. Please call us at 608-257-0099 before brewing if any item is missing. Thanks!

## Directions

**Sanitize everything well! Remember to stir periodically throughout the boil!**

0. If you are using liquid yeast, about three to six hours before you are going to brew, remove the liquid yeast from the refrigerator. If it is a Wyeast pack, break the nutrient pack inside the yeast package according to the directions on the package. Leave the yeast out at room temperature until it is time to pitch your yeast into your beer.
1. Fill your kettle with 10 quarts of cold water and then turn on the heat and bring the mixture to a boil. (**Note:** If your brew system allows you to boil more than 8 quarts, feel free to boil more liquid. This will allow you to get a bit better utilization from your hops and reduce caramelization). You will be boiling the mixture, called wort, for a total of 30 minutes. However, keep reading, because you'll be adding hops during that time.
2. When you achieve a boil, turn off the heat and empty the **Goldpils Vienna liquid malt extract** into the hot water. (Extract may pour more easily if you open the top of the container and place it in a saucepan of hot, not boiling, water for ten minutes prior to pouring. Do not apply direct heat to the jar). Stir extract into wort well.
3. Turn the heat back on and bring the wort to a boil. Upon initial boil the wort may foam up (called a "hot break"). If this happens, reduce the heat until the foam recedes, then turn up the heat, bring back to a boil, and maintain a rolling boil. Start your 30 minute timer at this point in the brewing process.
4. Add **1 oz of Chinook** hop pellets and boil the wort for 25 minutes. This hop addition will impart most of the bitterness to your beer.
5. After 25 minutes, turn off the heat. You will now add the **Pale Ale dry malt extract**. Make sure everything is stirred in well. Turn the heat back on, bring the wort to a boil, and boil for 5 more minutes.
6. After these 5 minutes (30 minutes total), you are done boiling your beer, so it's time to turn off the heat. As you turn off the heat, add **1 oz Mosaic** and **1 oz Amarillo** hop pellets. Start to cool the hot wort down by placing the pot carefully into a sink of ice water for 15-30 minutes or by using a wort chiller.
7. Sanitize fermentor, stopper, and air lock with sanitizing material according to its directions.

8. Fill the sanitized fermentor with 2.5 gallons of cold water (use less if you boiled more water than the recipe calls for). Check the temperature of your wort. Once it is 110-120F (or lower if you're using less top up water), carefully pour or siphon the chilled wort into the cold water in the fermentor. If necessary, top up to 5 - 5.25 gallons with cold water.
9. Take a temperature reading of the wort. If the wort mixture in the fermentor is below 80°F (not warm to the touch), give the wort a good shake or a good stir with a sanitized metal or plastic spoon. Here you are trying to aerate the wort, which will help your yeast get going. This is also a good time to take a hydrometer reading. The number from this reading is your starting gravity. Add your beer **yeast**. Instructions are on the yeast package.
10. Seal your fermentor. Attach the fermentation lock half filled with water. Ferment at 66°-72°F for around 14 days. Note that it can take up to 24 hours for active fermentation to be visible. If you don't see any activity in the air lock or foam on the surface of beer after 24 hours, call us at 608-257-0099. If doing a double stage fermentation, siphon the beer into the glass carboy after 5-7 days in the primary fermentor (the beer may be transferred to the glass carboy as soon as the foam has fallen far enough so the carboy will not overflow).
11. However you ferment, add the **1 oz Mosaic** hop pellets to your beer after about 7 -10 days of fermentation (if doing two-stage fermentation, add these hops when you siphon your beer into the secondary fermentor).
12. Allow the Mosaic dry hops to stay in contact with the beer for 3-5 days. After 3-5 days, if your beer has ceased fermentation, you can go ahead and bottle or keg your beer. Whether you bottle or keg, sanitize everything that will contact the beer during packaging, including bottles, caps, kegs, siphon tubing, bottle filler, etc. Also, now is a good time to take a hydrometer reading. This would be your beer's final gravity.
  - a. **Bottling, Single-Stage Fermentor:** Siphon beer into sanitized bottles. Pour just under 1 tsp. corn sugar in each bottle. Cap and turn bottles upside down several times to mix in sugar.
  - b. **Bottling, 2-Stage Fermentor:** Rack the beer carefully off the sediment into a sterilized fermentor or bottling bucket from the carboy. Bring ¾ pint of water to a boil. Turn off heat. Dissolve 1 cup of corn sugar in this hot water and stir gently into the beer. Bottle and cap.
  - c. **Kegging:** Siphon the beer into your sanitized keg, purge the oxygen from the head-space, hook up to your CO2, wait, and enjoy!
13. Store upright at room temperature (~70F) for 14 days to carbonate. Beer may then be stored at cooler temperatures to age. Beer may be consumed at any time, though it will continue to improve for several weeks.