



# Vintage's Scaredy Cat Oatmeal Stout

Appx. Values: O.G.: 1.059 F.G.: 1.016 ABV: 5.7% IBU: 34 SRM: 41

⚠ If your kit has **liquid yeast**, put it in the refrigerator as soon as possible.

Dark beer lovers rejoice! The Vintage's pitch black stout is packed with the rich malt flavors of chocolate, caramel, molasses and espresso and is brewed with a large portion of rolled oats for a well-rounded, "chewy" mouthfeel. Hearty and robust, Scaredy Cat is no scrawny little kitty. Make sure you stop by the Vintage Brewing Co. at 674 S. Whitney Way in Madison and compare your version to the real thing.

## Kit Ingredients

- Specialty Steeping Grains:
  - 19 oz Flaked Oats
  - 12 oz Chocolate malt
  - 11 oz Caramel 80L malt
  - 10 oz Roast Barley
  - 4 oz Carapils/Dextrine
  - 2 oz Black malt
  - 2 oz Honey malt
- 3.3 lb Munich malt extract
- 3-3.3 lb golden light liq. extract
- 1 lb golden light dry extract
- 1 oz Brewers Gold hops (60 min)
- 2 oz Cascade hops (½ oz at 60 min, ½ oz at 30 min, 1 oz at 10 min)
- 1 cup corn sugar (for bottling)
- 2 Muslin sacks to steep grains
- Safale S-04 dry, Wyeast 1028, WLP005, OYL-006, or GY011 yeast

⚠ Please make sure that your kit contains these items. Please call us at 608-257-0099 before brewing if any item is missing. Thanks!

## Directions

**Sanitize everything well! Remember to stir periodically throughout the boil!**

0. If you are using liquid yeast, about three to six hours before you are going to brew, remove the liquid yeast from the refrigerator. If it is a Wyeast pack, break the nutrient pack inside the yeast package according to the directions on the package. Leave the yeast out at room temperature until it is time to pitch your yeast into your beer.
1. Fill your kettle with 10 quarts of cold water, pour the crushed **steeping grain** into the grain sack, tie the sack closed, and place it into your kettle (**Note:** If your brew system allows you to boil more than 8 quarts, feel free to boil more liquid. This will allow you to get a bit better utilization from your hops and reduce caramelization). Turn on heat and bring mixture to 155F and then turn off heat. Steep the grains for 20 minutes. Do **not boil** grains.
2. While grains are steeping, heat 6 quarts of water to 170F in a separate pot. After the 20 minute steep, remove the grains from the mixture and rinse (sparge) them with the 6 quarts of hot water, collecting the runnings in your boil kettle. Then turn on the heat and bring the mixture to a boil. You will be boiling the mixture, called wort, for a total of 60 minutes. However, keep reading, because you'll be adding hops during that time.
3. When you achieve a boil, turn off the heat and empty all the **golden light** and **munch malt extract** into the hot water. (Extract may pour more easily if you open the top of the container



and place it in a saucepan of hot, not boiling, water for ten minutes prior to pouring. Do not apply direct heat to the jar). Stir extract into wort well.

4. Turn the heat back on and bring the wort to a boil. Upon initial boil the wort may foam up (called a “hot break”). If this happens, reduce the heat until the foam recedes, then turn up the heat, bring back to a boil, and maintain a rolling boil. Start your 60 minute boil timer now. Add **1 oz of Brewers Gold** and **1/2 oz Cascade** hop pellets and boil the wort for 30 minutes. This hop addition will impart most of the bitterness to your beer.
5. After these 30 minutes, it’s time to add more hops. Add **1/2 oz Cascade** hop pellets and boil for 20 more minutes.
6. After these 20 minutes (50 minutes total), add **1 oz Cascade** hop pellets and boil 10 minutes more.
7. After these 10 minutes (60 minutes total), you are done boiling your beer, so it’s time to turn off the heat and start to cool the wort down.
8. Sanitize fermentor, stopper, and air lock with sanitizing material according to its directions.
9. Fill the sanitized fermentor with 2.5 gallons of cold water (use less if you boiled more water than the recipe calls for). Cool your hot wort down to around 110-120F by placing your pot carefully into a sink of ice water for 15-30 minutes or by using a wort chiller. Carefully pour the hot wort into the cold water in the fermentor. If necessary, top up to 5 gallons with cold water.
10. Take a temperature reading of the wort. If the wort mixture in the fermentor is below 80°F (not warm to the touch), give the wort a good shake or a good stir with a sanitized metal or plastic spoon. Here you are trying to aerate the wort, which will help your yeast get going. This is also a good time to take a hydrometer reading. The number from this reading is your starting gravity. Add your beer **yeast**. Instructions are on the yeast package.
11. Seal your fermentor. Attach the fermentation lock half filled with water. Ferment at 60°-72°F for around 14 days. Note that it can take up to 24 hours for active fermentation to be visible. If you don’t see any activity in the air lock or foam on the surface of beer after 24 hours, call us at 608-257-0099. If doing a double stage fermentation, siphon the beer into the glass carboy after 5-7 days in the primary fermentor (the beer may be transferred to the glass carboy as soon as the foam has fallen far enough so the carboy will not overflow).
12. After 14 days, if your beer has ceased fermentation, you can go ahead and bottle or keg your beer. Whether you bottle or keg, sanitize everything that will contact the beer during packaging, including bottles, caps, kegs, siphon tubing, bottle filler, etc. Also, now is a good time to take a hydrometer reading. This would be your beer’s final gravity.
  - a. **Bottling, Single-Stage Fermentor:** Siphon beer into sanitized bottles. Pour just under 1 tsp. corn sugar in each bottle. Cap and turn bottles upside down several times to mix in sugar.
  - b. **Bottling, 2-Stage Fermentor:** Rack the beer carefully off the sediment into a sterilized fermentor or bottling bucket from the carboy. Bring ¾ pint of water to a boil. Turn off heat. Dissolve 1 cup of corn sugar in this hot water and stir gently into the beer. Bottle and cap.
  - c. **Kegging:** Siphon the beer into your sanitized keg, purge the oxygen from the head-space, hook up to your CO2, wait, and enjoy!
13. Store upright at room temperature (~70F) for 14 days to carbonate. Beer may then be stored at cooler temperatures to age. Beer may be consumed at any time, though it will continue to improve for several weeks.