



WINE AND HOP SHOP SUCKS

⚠ If your kit has **liquid yeast**, put it in the refrigerator as soon as possible.

"...We found in that darkness, the spark of inspiration that would yield up this nearly sanctified recipe!"
~Lagunitas Brewing Company

A clone of a popular West Coast IPA, this ale is a 'cereal medley' of barley, wheat, oats, and rye and is bursting with resinous, citrusy hop flavor and aroma.

Calculated Approximate: O.G.: 1.067 F.G.: 1.016 ABV: 7.0% IBU: 63 SRM: 5

Kit Ingredients

- Specialty Steeping Grains:
 - 8 oz Pale Ale malt
 - 8 oz Goldpils Vienna
 - 4 oz BE Cara 20L malt
 - 4 oz Flaked Oats
 - 4 oz Flaked Rye
- 7 lb Pilsen liquid malt extract
- 1 oz Chinook hops (½ at 60, 10 min)
- 1 oz Simcoe hops (½ at 20 min, dry hop)
- 1 oz Amarillo hops (½ at 10, 0 min)
- 1 oz Citra hops (½ at 5, 0 min)
- 1 oz Mosaic hops (½ at 5, dry hop)
- 1 lb wheat dry malt extract
- Muslin sack to steep grains
- 1 cup corn sugar (for bottling)
- Dry Yeast US-05, Wyeast 1056, WLP001, Omega Yeast OYL-004, or GigaYeast GY001

⚠ Please make sure that your kit contains these items. Please call us at 608-257-0099 before brewing if any item is missing. Thanks!

Directions

Sanitize everything well! Remember to stir periodically throughout the boil!

0. If you are using liquid yeast, about three to six hours before you are going to brew, remove the liquid yeast from the refrigerator. If it is a Wyeast pack, break the nutrient pack inside the yeast package according to the directions on the package. Leave the yeast out at room temperature until it is time to pitch your yeast into your beer.
1. Fill your kettle with 8 quarts of cold water, pour the crushed **steeping grain** into the grain sack, tie the sack closed, and place it into your kettle (**Note:** If your brew system allows you to boil more than 8 quarts, feel free to boil more liquid. This will allow you to get a bit better utilization from your hops and reduce caramelization). Turn on heat and bring mixture to 152F and then turn off heat. Steep the grains for 30 minutes. Do **not boil** grains.
2. While your grains are steeping, heat 4 quarts of water to 170F in a separate pot. After the 30 minute steep, **remove the grains** from the mixture and sparge by rinsing them with the 4 quarts of hot water, collecting the runnings in your boil kettle. Then turn on the heat and bring the mixture to a boil. You will be boiling the mixture, called wort, for a total of 60 minutes. However, keep reading, because you'll be adding hops during that time.
3. When you achieve a boil, turn off the heat and pour **about half of the liquid malt extract** into the hot water. (Extract may pour more easily if you open the top of the container and place it in a saucepan of hot, not boiling, water for ten minutes prior to pouring. Do not apply direct heat to the jar). Stir extract into wort well.



4. Turn the heat back on and bring the wort to a boil. Upon initial boil the wort may foam up (called a “hot break”). If this happens, reduce the heat until the foam recedes, then turn up the heat, bring back to a boil, and maintain a rolling boil. Start your 60 minute timer at this point in the brewing process. Add **½ oz of Chinook** hop pellets and boil the wort for 40 minutes. This hop addition will impart most of the bitterness to your beer.
5. After these 40 minutes, add **½ oz Simcoe** hop pellets and continue boiling for another 10 minutes.
6. After these 10 minutes (50 minutes total), add **½ oz Amarillo** and the remaining **½ oz Chinook** hop pellets and continue boiling for another 5 minutes.
7. After these 5 minutes (55 minutes total), turn off the heat. You will now add the **remaining half of the liquid malt extract, 1 lb wheat dry malt extract, ½ oz Mosaic** and **½ oz Citra** hop pellets. Make sure everything is stirred in well. Turn the heat back on, bring the wort to a boil, and boil for 5 more minutes.
8. After these 5 minutes (60 minutes total), you are done boiling your beer, so it’s time to turn off the heat. As you turn off the heat, add the remaining **½ oz Citra** and **½ oz Amarillo** hop pellets. (Put the remaining ½ oz each of Simcoe and Mosaic hop pellets in an airtight storage container and save for dry hopping). Start to cool the hot wort down by placing the pot carefully into a sink of ice water for 15-30 minutes or by using a wort chiller.
9. Sanitize fermentor, stopper, and air lock with sanitizing material according to its directions.
10. Fill the sanitized fermentor with 2.5 gallons of cold water (use less if you boiled more water than the recipe calls for). Check the temperature of your wort. Once it is 110-120F (or lower if you’re using less top up water), carefully pour or siphon the chilled wort into the cold water in the fermentor. If necessary, top up to 5 gallons with cold water.
11. Take a temperature reading of the wort. If the wort mixture in the fermentor is below 80°F (not warm to the touch), give the wort a good shake or a good stir with a sanitized metal or plastic spoon. Here you are trying to aerate the wort, which will help your yeast get going. This is also a good time to take a hydrometer reading. The number from this reading is your starting gravity. Add your beer **yeast**. Instructions are on the yeast package.
12. Seal your fermentor. Attach the fermentation lock half filled with water. Ferment at 66°-72°F for around 14 days. Note that it can take up to 24 hours for active fermentation to be visible. If you don’t see any activity in the air lock or foam on the surface of beer after 24 hours, call us at 608-257-0099. If doing a double stage fermentation, siphon the beer into the glass carboy after 5-7 days in the primary fermentor (the beer may be transferred to the glass carboy as soon as the foam has fallen far enough so the carboy will not overflow).
13. However you ferment, add the saved **½ oz Mosaic and ½ oz Simcoe** hop pellets to your beer after about 7 days of fermentation (if doing two-stage fermentation, add these hops when you siphon your beer into the secondary fermentor).
14. After around 14 days, if your beer has ceased fermentation, you can go ahead and bottle or keg your beer. Whether you bottle or keg, sanitize everything that will contact the beer during packaging, including bottles, caps, kegs, siphon tubing, bottle filler, etc. Also, now is a good time to take a hydrometer reading. This would be your beer’s final gravity.
 - a. **Bottling, Single-Stage Fermentor:** Siphon beer into sanitized bottles. Pour just under 1 tsp. corn sugar in each bottle. Cap and turn bottles upside down several times to mix in sugar.
 - b. **Bottling, 2-Stage Fermentor:** Rack the beer carefully off the sediment into a sterilized fermentor or bottling bucket from the carboy. Bring ¾ pint of water to a boil. Turn off heat. Dissolve 1 cup of corn sugar in this hot water and stir gently into the beer. Bottle and cap.

- c. **Kegging:** Siphon the beer into your sanitized keg, purge the oxygen from the head-space, hook up to your CO2, wait, and enjoy!
15. Store upright at room temperature (~70F) for 14 days to carbonate. Beer may then be stored at cooler temperatures to age. Beer may be consumed at any time, though it will continue to improve for several weeks.