

Directions

Measurements are ml/cc per reservoir. PPM levels are in addition to your standard water PPM levels.
The recommended pH level is between 5.4 and 6.1 depending on what stage the plant is in.

VEG	BLOOMBOX		11 Litre			
WEEK	1	2	3	4		
*Bronze Package						
Micro	13.75	16.5	19.25	22		
Grow	20.5	27.5	33	38.5		
Bloom	5.5	8.25	9.6	11		
PPM Level	706	900	976	1187		
*Silver Package						
Super B +	11	11	22	22		
Carbo Blast		5.5	5.5	11		
PPM Level	790	942	1142	1261		
*Gold Package						
Prop-O-Gator	17.2	24.1	27.5	27.5		
Royal Gold	11	11	11	22		
Plantacillin	5.5	5.5	11	11		
PPM Level	828	1047	1293	1395		

VEG	BLOOMBOX		23 Litre			
WEEK	1	2	3	4		
*Bronze Package						
Micro	28.75	34.5	40.25	46		
Grow	43.1	57.5	69	80.5		
Bloom	11.5	17.25	20.1	23		
PPM Level	706	900	976	1187		
*Silver Package						
Super B +	23	23	46	46		
Carbo Blast		11.5	11.5	23		
PPM Level	790	942	1142	1261		
*Gold Package						
Prop-O-Gator	35.9	50.3	57.5	57.5		
Royal Gold	23	23	23	46		
Plantacillin	11.5	11.5	23	23		
PPM Level	828	1047	1293	1395		

FLOWER	BLOOMBOX		23 Litre					
WEEK	1	2	3	4	5	6	7	8
*Bronze Package								
Micro	34.5	40.25	40.25	46	46	46	34.5	FLUSH
Grow	17.25	17.25	17.25	17.25	17.25	11.5	5.75	
Bloom	51.75	51.75	51.75	97.75	97.75	109.25	120.75	
PPM Level	795	877	877	1169	1152	1143	1065	

If only using Bronze and Silver packages, use Bud Boom in Week 3 of Flower and disregard Bud Start and Ton O Bud use

FLOWER	BLOOMBOX		23 Litre					
WEEK	1	2	3	4	5	6	7	8
*Silver Package								
Super B +	34.5	34.5	34.5	34.5	34.5	34.5	34.5	FLUSH
Carbo Blast	46	46	46	46	46	46	46	
Bud Boom						46	46	
PPM Level	862	943	943	1244	1226	1223	1135	

If only using Bronze and Silver packages, use Bud Boom in Week 3 of Flower and disregard Bud Start and Ton O Bud use

FLOWER	BLOOMBOX		23 Litre					
WEEK	1	2	3	4	5	6	7	8
*Gold Package								
Calnesium	34.5	34.5	34.5	23	23	23	23	FLUSH
Royal Gold	46	46	46	46	46	46	46	
Plantacillin	46	46	46	46	46	46	46	
Bud Start		46	46					
Ton-O-Bud				46	46			
PPM Level	1147	1268	1268	1610	1588	1467	1395	

If only using Bronze and Silver packages, use Bud Boom in Week 3 of Flower and disregard Bud Start and Ton O Bud use

If the plants are not ready after week 7, repeat in week 8 then flush in week 9.
Do not exceed the recommended measurements when adding the nutrients and additives.