

CBD IPA

Let us be perfectly blunt with you: our CBD Beer is dope. Made with the purest CBD (Columbus, Bravo, and Denali hops), this beer is, like, a chill version of a West Coast IPA. Three seriously dank hops combine to make a chronically delicious brew, with delicate notes of herb, grass, and flowers. Pairs perfectly with pizza. Or White Castle. Or pizza on a White Castle burger. Wait. That's an incredible idea. Someone write that down.

O.G: 1.064 | **BREW TIME 6 WEEKS:** 2 WEEKS PRIMARY | 2 WEEKS SECONDARY | 2 WEEKS BOTTLE CONDITIONING



KIT INVENTORY

SPECIALTY STEEPING GRAIN

- 0.5 lbs Briess Caramel 20L

MALT EXTRACTS

- 6 lbs Gold Malt Syrup
- 3.15 lbs Gold Malt Syrup

PREMIUM HOPS

- 1 oz Bravo (60 min)
- 1 oz Columbus (10 min)
- 1 oz Denali (10 min)
- 1 oz Columbus (0 min)
- 1 oz Denali (0 min)
- 1 oz Columbus (dry hop)
- 1 oz Denali (dry hop)

YEAST

Dry Yeast:

- Fermentis Safale US-05. Optimum Temp: 59° - 75°F

Liquid Yeast Options:

- Imperial Yeast A07 Flagship. Optimum temp: 60° - 72°F
- Omega Yeast OYL-004 West Coast Ale I. Optimum temp: 60° - 73°F

UPON ARRIVAL UNPACK THE KIT

- Be sure you have all items listed in the Kit Inventory (above)
- Refrigerate the yeast
- Contact us immediately if you have any questions or concerns!

READ ALL INSTRUCTIONS BEFORE STARTING

YOU WILL NEED:

- Homebrewing starter kit for brewing 5 gallon batches
- Boiling kettle of at least 3.5 gallons capacity
- 5 gallon carboy, with bung and airlock, to use as a secondary fermenter. NOTE: You may skip transferring to a carboy and leave the beer in the primary fermenter. See step 17
- Approximately two cases of either 12 oz or 22 oz pry-off style beer bottles

A FEW HOURS BEFORE BREW DAY

Remove the liquid yeast packages from the refrigerator, and leave it in a warm place (~70°F) to come to pitching temperature. If you are using Wyeast, smack the packs as shown on the back of the package and allow to swell for at least 3 hours. Do not brew with inactive yeast - contact customer service for advice or a replacement. If you are using dry yeast, no action is needed.

ON BREWING DAY

1. Heat 2.5 gallons of water.
2. Pour crushed grain into the supplied mesh bag, and tie the open end in a knot. Steep for 30 minutes at 150° - 160°F. Remove bag, drain and discard.
3. Bring to a boil, remove the kettle from the burner and stir in the 6 lbs Gold Malt Syrup and 3.15 lbs Gold Malt Syrup.
4. Return wort to boil. The mixture is now called "wort", the brewer's term for unfermented beer. NOTE: Total boil time for this recipe is 60 minutes.
 - Add 1 oz Bravo at the beginning of the boil.
 - Add 1 oz Columbus and 1 oz Denali with 10 minutes remaining in the boil.
 - Add 1 oz Columbus and 1 oz Denali with 0 minutes remaining in the boil. Remove from heat and allow to steep for 5 minutes before chilling.
5. Cool the wort. When the 60 minute boil and 5 minute hopstand is finished, cool the wort to approximately 70°F as rapidly as possible. Use a wort chiller, or put the kettle in an ice bath in your sink.
6. Sanitize fermenting equipment and yeast pack. While the wort cools, sanitize the fermenting equipment – fermenter, lid or stopper, airlock, funnel, etc – along with the yeast pack.

ON BREWING DAY – CONTINUED

7. Fill primary fermenter with 2 gallons of cold water, then pour in the cooled wort. Leave any thick sludge in the bottom of the kettle.
8. Add more cold water as needed to bring the volume to 5 gallons.
9. Aerate the wort. Seal the fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.
10. Measure specific gravity of the wort with a hydrometer and record in the "BREWERS NOTES" section.
11. Add yeast once the temperature of the wort is between 65° and 70°F. Sanitize and open the yeast pack and carefully pour the contents into the primary fermenter.
12. Seal the fermenter. Add approximately 1 tablespoon of water to the sanitized fermentation lock. Insert the airlock into rubber stopper or lid, and seal the fermenter.

PRIMARY FERMENTATION

13. Active fermentation begins. Within approximately 48 hours of Brewing Day, active fermentation will begin – there will be a cap of foam on the surface of the beer, the specific gravity as measured with a hydrometer will drop steadily, and you may see bubbles come through the fermentation lock. The optimum fermentation temperature for this beer is 65° - 70° F. Move the fermenter to a warmer or cooler spot as needed.
14. Active fermentation ends. Approximately one to two weeks after brewing day, active fermentation will end. When the cap of foam falls back into the new beer, bubbling in the air lock slows down or stops, and the specific gravity as measured with a hydrometer is stable, proceed to the next step.
15. Optional - Transfer beer to secondary fermenter. Sanitize siphoning equipment and an airlock and carboy bung or stopper. Siphon the beer from the primary fermenter into the secondary. If you do not have a secondary fermenter, simply leave the beer in the primary fermenter.

SECONDARY FERMENTATION - OPTIONAL *

16. Allow the beer to condition in the secondary fermenter for 2 weeks before proceeding with the next step. Timing now is somewhat flexible. * See the "YOU WILL NEED" section and step 16 above. Add 1 oz each of Columbus and Denali hops directly to the fermenter 5-7 days before bottling day.

BOTTLING DAY - ABOUT 4 WEEKS AFTER BREWING DAY

17. Sanitize siphoning and bottling equipment.
18. Mix a priming solution (a measured amount of sugar dissolved in water to carbonate the bottled beer). Use the following amounts, depending on which type of sugar you will use:
 - Corn sugar (dextrose) 2/3 cup in 16 oz water.
 - Table sugar (sucrose) 5/8 cup in 16 oz water.
 Bring the solution to a boil and pour into the bottling bucket.
19. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix—don't splash.
20. Fill and cap bottles.

CONDITIONING - ABOUT 6 WEEKS AFTER BREWING DAY

21. Condition bottles at room temperature for 1–2 weeks. After this point, the bottles can be stored cool or cold.
22. Serving. Pour into a clean glass, being careful to leave the layer of sediment at the bottom of the bottle. Cheers!

BREWERS NOTES

At Northern Brewer, we've always got your back. Our Brewmasters are available 7 days a week to help you brew your very best, and it doesn't end until you're completely happy with your latest batch...and looking forward to the next one. We'll never let you fail. Guaranteed.