



NORTHERN BREWER

<b>O.G.</b>	<b>ABV</b>	<b>IBU</b>	<b>BREW TIME: 8 WEEKS</b>
1.100	11%	85	Primary: 3 Weeks
			Secondary: 3 Weeks
			Bottle Conditioning: 2 Weeks

# DOUBLE DEAD RINGER IPA

Doubling down on our most popular recipe kit of all time, we took our famous Dead Ringer recipe and upped the ante - significantly. Double Dead Ringer is a real juggernaut coming in at ~11% ABV, 85 IBU and featuring a whopping 12 oz of an American classic, Centennial hops. The massive doses of Centennial create a firm bitterness and a huge grapefruit citrus, floral and slightly earthy aroma and flavor balanced by an aggressive malt profile of slightly crusty bread with undertones of sweet caramel and toffee. This imperial IPA is not for the faint of heart.

## KIT INVENTORY

### GRAIN BILL

- 20 lbs Rahr 2-Row Malt
- 1 lb Caramel 40L

### PREMIUM HOPS & OTHER

#### ADDITIONS

- 1 oz Centennial **60 min**
- 3 oz Centennial **20 min**
- 1 lb Corn Sugar **10 min**
- 5 oz Centennial **5 min**
- 3 oz Centennial **Dry hop**

## SUGGESTED YEAST

### YEAST

DRY YEAST:  
**Fermentis Safale US-05**  
 Optimum Temp: 59°- 75°F

LIQUID YEAST OPTIONS:  
**Imperial Yeast A07 Flagship**  
 Optimum temp: 60°- 72°F

**Omega Yeast OYL-004 West Coast Ale I**  
 Optimum temp: 60°- 73°F

## BEFORE BREW DAY

- **IMPORTANT:** This kit is formulated to produce 6 gallons of wort to account for the huge amount of hops.
- Upon arrival, unpack kit.
- Read all instructions before starting.
- Be sure you have all items listed in the Kit Inventory.
- Refrigerate liquid yeast.
- If making a yeast starter, we suggest 24-48 hrs.
- Contact us if you have any questions or concerns.

## YOU WILL NEED

- Homebrewing equipment for brewing 5 gallon batches.
- All-grain equipment kit with mash tun and hot liquor tank
- Boiling kettle (at least 8 gallon capacity).
- Approx. 2 cases of 12 oz or 22 oz pry-off beer bottles.
- **Optional** - 6 gallon carboy, with bung and airlock, to use as secondary fermentor.

## A FEW HOURS BEFORE BREW DAY

Remove liquid yeast packages from the refrigerator. Leave in warm place (~70°F). Check yeast instructions on packet.

## BREWING NOTES

---



---



---



---



---



---

## KEY STATS

Brew Day Date: \_\_\_\_\_

Secondary: \_\_\_\_\_

Important Additions: \_\_\_\_\_

Bottling/Kegging: \_\_\_\_\_

Fermentation Temp: \_\_\_\_\_

Yeast Strain #: \_\_\_\_\_

Measured OG: \_\_\_\_\_ FG: \_\_\_\_\_

## MASH SCHEDULE

### SINGLE INFUSION

If you are new to all-grain, we suggest starting with 1.5 quarts of water per pound of grain for strike water volume. This mash thickness can be adjusted for future brews as you become more comfortable with your equipment.

**Saccharification Rest:** 148° F for 60 minutes

**Mashout:** 170° F for 10 minutes (optional)

To raise the temp for mashout, gently apply direct heat while stirring well (if using a kettle), or add near boiling water until target temp is reached.

Prepare sparge water in hot liquor tank at 1 quart per pound of grain. Perform a fly sparge until you reach pre-boil volume (7-8 gallons) in your kettle. Sparge should take about an hour for optimal extraction efficiency. You should end with extra sparge water in hot liquor tank. Use this hot water to clean later on.

### BOIL ADDITIONS & TIMES

Total time: 60 mins

- |  |                                       |
|--|---------------------------------------|
| - 1 oz Centennial<br>Beginning of boil | - 1 lb Corn Sugar 10<br>min remaining |
| - 3 oz Centennial 20<br>min remaining  | - 5 oz Centennial 5<br>min remaining  |

### AFTER THE BOIL

1. When 60 minute boil is finished, remove from heat.
2. Cool wort to 65°-70°F ASAP.
3. Sanitize fermenting equipment and yeast pack(s): While wort cools, sanitize fermenting equipment (fermenter, lid or stopper, airlock, funnel, etc) along with yeast pack.
4. Transfer cooled wort into primary fermentation vessel using valve on boil kettle, siphoning from boil kettle, OR pouring wort into fermenter.
5. Aerate wort. Seal fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.
6. Measure specific gravity of wort with a hydrometer. Record. Target gravity for this kit is 1.100.
7. Add yeast once temp of wort is between 65°-70°F. Sanitize and open yeast pack(s). Carefully pour contents into primary fermenter.
8. Seal fermenter. Add 1 tbsp of sanitizer or clean water to sanitized airlock. Insert airlock into rubber stopper or bucket lid. Seal fermenter.
9. Move fermenter to a warm, dark, quiet spot until fermentation begins.

### PRIMARY FERMENTATION

10. **Within 48 hours Active fermentation begins.**  
You'll see a cap of foam on the surface of the beer. Specific gravity as measured with a hydrometer will drop steadily. You may see bubbles in the fermentation lock. The optimum temp. for this beer is 65°- 70°F.
11. **Within 2-3 weeks Active fermentation ends.**  
Proceed to next step when:
  - Cap of foam falls back into the beer.
  - Bubbling in airlock slows down or stops.
  - Specific gravity as measured with a hydrometer is stable.

### SECONDARY FERMENTATION (OPTIONAL)

**NOTE:** You may skip secondary fermentation and simply add 3 weeks to primary fermentation before bottling.

12. Sanitize siphoning equipment, airlock, carboy bung or stopper. Siphon beer from primary fermenter into secondary. Add **3 oz Centennial hops** directly to the new beer.
13. Allow beer to condition in secondary fermenter for 3 weeks before proceeding with the next step. Timing is now somewhat flexible.

### BOTTLING DAY (ABOUT 4 WEEKS AFTER BREWING DAY)

14. Sanitize siphoning and bottling equipment.
15. Mix a priming solution (sugar dissolved in water; carbonates bottled beer). Use the following amounts, depending on which type of sugar you use:
  - Corn sugar (dextrose) 2/3 cup in 16oz water.
  - Table sugar (sucrose) 5/8 cup in 16oz water.Bring solution to a boil. Pour into bottling bucket.
16. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix
  - do not splash.
17. Fill and cap bottles.

### CONDITIONING (ABOUT 6 WEEKS AFTER BREWING DAY)

18. Condition bottles at room temp. for 1-2 weeks. After this point, store bottles cool or cold.
19. Serving: Pour into a clean glass. Be careful to leave any sediment at the bottom of the bottle. Cheers!

## WE'VE GOT YOUR BATCH

We're so confident in the quality of our beer kits, we'll replace any kit, anytime, no questions asked.

## CONNECT TO OUR COMMUNITY

Snap and share your brew, we know you're proud.  
**#NorthernBrewer** NorthernBrewer.com