


NON-SLIP Skinny 10" Curvy Log Cabin Trim Tool



Create the illusion of curves with this Skinny 10" Curvy Log Cabin Trim Tool.
By trimming after each round, you'll have a perfect 10" finished square every time.

Designed by Jean Ann Wright

#CGRJAW14
Made in USA



SEE A DEMO
SCAN WITH ANY
QR READER



Creative Grids® USA, Inc.
400 W. Dussel Dr. Ste B,
Maumee, OH 43537
www.creativegridsUSA.com

Creative Grids® UK, Ltd.
Unit 23A Pate Road
Leicester Road Industrial Estate
Melton Mowbray
Leicestershire, LE13 0RG England
www.creativegrids.com

Creative Grids is covered by U.S. Trademark Registration No. 2,796,615

NON-SLIP Skinny 10" Curvy Log Cabin Trim Tool

Center Squares: Cut a precise 1-3/4" square.

Cutting Strips: Strips can be cut from 2-1/2" precuts, fat quarters, scraps or yardage. Strips can be cut to the lengths given in the charts below or stitched in place and then trimmed to size.

Helpful Tools: Rotating rotary cutting mat and rotary cutter

Skinny 10" Curvy Log Cabin

Wide Logs Added First

Center Square - 1-3/4"

2" Wide Strips & 1-1/2" Narrow Strips


Round 1	1st Wide	2" x 1-3/4"
	2nd Wide	2" x 3-1/4"
	1st Narrow	1-1/2" x 3-1/4"
	2nd Narrow	1-1/2" x 4-1/4"

Round 2	1st Wide	2" x 3-1/2"
	2nd Wide	2" x 5"
	1st Narrow	1-1/2" x 5"
	2nd Narrow	1-1/2" x 6"

Round 3	1st Wide	2" x 5-1/4"
	2nd Wide	2" x 6-3/4"
	1st Narrow	1-1/2" x 6-3/4"
	2nd Narrow	1-1/2" x 7-3/4"

Round 4	1st Wide	2" x 7"
	2nd Wide	2" x 8-1/2"
	1st Narrow	1-1/2" x 8-1/2"
	2nd Narrow	1-1/2" x 9-1/2"

Round 5	1st Wide	2" x 8-3/4"
	2nd Wide	2" x 10-1/4"
	1st Narrow	1-1/2" x 10-1/4"
	2nd Narrow	1-1/2" x 11-1/4"



Skinny 10" Curvy Log Cabin

Narrow Logs Added First

Center Square - 1-3/4"

1-1/2" Narrow Strips & 2" Wide Strips


Round 1	1st Narrow	1-1/2" x 1-3/4"
	2nd Narrow	1-1/2" x 2-3/4"
	1st Wide	2" x 2-3/4"
	2nd Wide	2" x 4-1/4"

Round 2	1st Narrow	1-1/2" x 3-1/2"
	2nd Narrow	1-1/2" x 4-1/2"
	1st Wide	2" x 4-1/2"
	2nd Wide	2" x 6"

Round 3	1st Narrow	1-1/2" x 5-1/4"
	2nd Narrow	1-1/2" x 6-1/4"
	1st Wide	2" x 6-1/4"
	2nd Wide	2" x 7-3/4"

Round 4	1st Narrow	1-1/2" x 7"
	2nd Narrow	1-1/2" x 8"
	1st Wide	2" x 8"
	2nd Wide	2" x 9-1/2"

Round 5	1st Narrow	1-1/2" x 8-3/4"
	2nd Narrow	1-1/2" x 9-3/4"
	1st Wide	2" x 9-3/4"
	2nd Wide	2" x 11-1/4"



Skinny 10" Curvy Log Cabin

Courthouse Steps

Center Square - 1-3/4"

1-1/2" Narrow Strips & 2" Wide Strips


Round 1	1st Wide	2" x 1-3/4"
	1st Narrow	1-1/2" x 1-3/4"
	2nd Wide	2" x 4-1/4"
	2nd Narrow	1-1/2" x 4-1/4"

Round 2	1st Wide	2" x 3-1/2"
	1st Narrow	1-1/2" x 3-1/2"
	2nd Wide	2" x 6"
	2nd Narrow	1-1/2" x 6"

Round 3	1st Wide	2" x 5-1/4"
	1st Narrow	1-1/2" x 5-1/4"
	2nd Wide	2" x 7-3/4"
	2nd Narrow	1-1/2" x 7-3/4"

Round 4	1st Wide	2" x 7"
	1st Narrow	1-1/2" x 7"
	2nd Wide	2" x 9-1/2"
	2nd Narrow	1-1/2" x 9-1/2"

Round 5	1st Wide	2" x 8-3/4"
	1st Narrow	1-1/2" x 8-3/4"
	2nd Wide	2" x 11-1/4"
	2nd Narrow	1-1/2" x 11-1/4"



Tips:

- Sew strips using a scant 1/4" seam allowance. Position center square on top of the first strip with right sides together and stitch in place. Continue to place block on top of strips throughout block construction.
- Always fold the strips away from the center and press before adding next strip.
- Strips are added in a clockwise direction around the center square. Add each consecutive round of strips in the same direction as the first round. You can start with two narrow strips, or two wide strips.

Note: Our diagrams show beginning each round with 2 wide strips, then 2 narrow strips to make a round. The order of adding strips can be reversed to begin with 2 narrow strips, then adding 2 wide strips for each round. Feel free to be creative.


NON-SLIP Skinny 10" Curvy Log Cabin Trim Tool Cont.

Round 1

Sew: Attach two wide strips, then two narrow strips in a clockwise direction around the center square. Press strips away from the center each time.

Trim: Position the Curvy Log Cabin Trim tool with the narrow strips of the block in the upper right corner. Position the centering square labeled "Narrow Round 1" over the center square of the block and trim up the right side and across the top. Turn the block and the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled "Wide Round 1".


Note: Be sure to line up the dotted lines on the ruler with the seam lines to keep your blocks nice and square.



Round 2

Sew: Attach two wide strips, then two narrow strips starting on the same side as you did in Round 1. Press strips away from the center.


Trim: Position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the Centering Square for "Narrow Round 2" over the center square of the block and trim up the right side and across the top. Turn the block and the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled "Wide Round 2".



Round 3

Sew: Attach two wide strips, then two narrow strips starting on the same side as you did in Rounds 1 and 2. Press strips away from the center.


Trim: Position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the Centering Square for "Narrow Round 3" over the center square of the block and trim up the right side and across the top. Turn the block and the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled "Wide Round 3".



Round 4

Sew: Attach two wide strips, then two narrow strips starting on the same side as you did in the previous rounds. Press strips away from the center.

Trim: Position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the Centering Square for "Narrow Round 4" over the center square of the block and trim up the right side and across the top. Turn the block and the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled "Wide Round 4".



Round 5

Sew: Attach the last two wide strips, then the last two narrow strips starting on the same side as you did in the previous rounds. Press strips away from the center.

Final Trim: Position the Curvy Log Cabin Trim tool with the Center Square Round 5 positioned on the center square of the block. Narrow strips should be in the top right corner for trimming. Trim around all four sides, rotating as needed for safe rotary cutting.

