NON-SLIP

4" Curvy Log Cabin Trim Tool

Create the illusion of curves with this 4" version of our popular Curvy Log Cabin Trim Tool Series.

Designed by Jean Ann Wright

CGRJAW6MINI

Made in USA





SEE A DEMO SCAN WITH ANY QR READER

Creative Grids® USA, Inc. 400 W. Dussel Dr. Ste B, Maumee, OH 43537 www.creativegridsUSA.com

Creative Grids® UK, Ltd. Unit 23A Pate Road Leicester Road Industrial Estate Melton Mowbray Leicestershire, LE13 ORG England www.creativegrids.com

NON-SLIP

4" Curvy Log Cabin Trim Tool Block size: 4" finished

Getting Started


Center squares: Cut a precise 1-1/8" square. (There is a template in the upper left corner of the 4" Curvy Log Cabin Trim Tool if you choose to use it.)

Narrow strips: Cut narrow strips 1-1/8" to 1-1/4" wide.

Wide strips: Cut wide strips 1-1/2" to 1-3/4" wide.

Tip: Sew the two wide strips in place around the center square first, then add two narrow strips.

Some patterns may indicate sewing the narrow strips in place first. Always follow the instructions on the pattern.




Align and trim strip ends

Sewing and Trimming Sequence for the Curvy Log Cabin Block

The blocks are constructed by adding each new strip in a clockwise direction. Sew all seams with a scant 1/4" seam allowance. As you add each strip, fold the new strip out with the seam allowances towards the outside edge. Press the seams as you sew.


Trimming Round 1

After adding two wide strips to the center square and two narrow strips, position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the Narrow Round 1 Centering Square over the center square of the block and trim up the right side and across the top.



Important tip: Be sure to line up the dotted lines on the ruler with the seam lines.

Turn the block **and** the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled Wide Round 1.




Trimming Round 2

After adding an additional round of wide and narrow strips, position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the Narrow Round 2 Centering Square over the center square of the block and trim up the right side and across the top.

Important tip: Be sure to line up the dotted lines on the ruler with the seam lines.




Turn the block and the ruler 180° (a half turn) and trim the wide strips in the same manner using the centering square labeled Wide Round 2.



Trimming Round 3

After adding the final round of wide and narrow strips, position the Curvy Log Cabin Trim tool with the narrow strips in the upper right corner. Position the labeled Center Square on the trim tool over the center square of the block and trim *all four sides*, turning both block and ruler together to keep the block aligned for the final trim.





Curvy Log Cabin Block



Creative Grids® is covered by U.S. Trademark Registration No. 2,796,615