

Extract Recipe

Adventures in Homebrewing - www.HomeBrewing.org 313 - 277 - 2739 (BREW)

Oskar Blues Pinner IPA

An easygoing, drinkable IPA that uses an array of hops to target its ever-evolving flavor. With tropical fruits, citrus juices, pineapple and spice berry up front in the aroma and flavor, the biscuit & toasted bread at the back balance out all the hops

K99-0211 Procedure: Please read all the instructions before you begin brewing, to ensure you have all the ingredients and fully understand the process.

Alcohol by Volume: 4.72 IBU: 71.59

Original Gravity: 1.049

Final Gravity: 1.012 Color SRM: 11.26

Clean Steep It is important to thoroughly clean and sanitize all of your brewing equipment

Begin by heating 2.5 gallons of water in your brew pot. Add speciality grains and tie a knot at one end of the "Grain Bag" leaving room for the grains to be loose in the bag. Place the Grain Bag in the

water. Slowly raise the temperature to 150° to 160°F (max temp.). Steep your grains at this temperature for 20 minutes. After 20 minutes, remove the "Grain Bag" from the pot. Do not squeeze the bag, just let the liquid drain from the bag into the pot. The water is now "Wort" at this point.

Grains:

3 lbs Cara Foam 15 oz Aromatic Malt

Fermentables & Start of Boil -Begin 60 minutes of boiling

Bring the "Wort" to a boil. It should be a rolling boil, but be careful to avoid a "Boil Over". Once you

achieved a boil, remove the brew pot from the heat source.

It is time to add the fermentables:

3 lbs Liquid Malt Extract Pale

1 lbs Dry Malt Extract Light

Fermentables:

Stir the extracts, and fermentables into the wort until it has all dissolved. It is important to make sure none of the extracts or fermentables are sitting on the bottom of the brew pot, as it will scorch when

returned to the heat source. Return the wort to a rolling boil and follow Hop Schedule:

			· ·	
Hop & Additive				
Schedule	Ounces	Hop/Additives	Hop Addition	Boil Time (minutes)
	1/2	3 HBU Pack	Boil/Bittering	80
	1/2	oz Apollo Hop Pellets	Knock-Out	Flame Out
	1/2	oz Cascade Hop Pellets	Knock-Out	Flame Out
	1	oz Mosaic (US) Hop Pellets	Dry	Add to Secondary
	1	oz Azacca Hop Pellets	Dry	Add to Secondary
	1	oz Citra Hop Pellets	Dry	Add to Secondary
	1	oz Calypso Pellet Hops	Dry	Add to Secondary
	1	oz El Dorado Hop Pellets	Dry	Add to Secondary

Cooling the wort and preparing the fermentor

Once the 60 minute boil is over, it is time to cool the wort. There are many ways to cool a wort, the AIH recommendation is a wort chiller. Cool the wort to approximately 100° F as quickly as possible.

The fermenting equipment needs to be sanitized. This can be done while the wort is cooling. Be sure to clean and sanitize the fermenters, airlock, lid, hose, hydrometer and test jar and rubber stopper. Anything that may come into contact with the wort should be

Transfer the wort into the primary fermenting vessel, then top off with cold water until a total of 5.125 gallons is in the primary fermenter. Aerate the wort at this point. This can be accomplished with an aeration stone or simply by rocking the fermenter back and forth once the lid is in place.

Take the reading	This is the time that you will want to take a specific gravity reading. Use a hydrometer and record the reading.					
Pitch the yeast	Once the wort is cooled to 78° F, it is safe to pitch the yeast. Pitch according the proper procedures of the type of yeast you have. Seal the fermenter tight. Attach the sanitized airlock and stopper.	Suggested Yeast :				
	Fill the airlock with water. Fermentation should begin within 24 - 48 hours. "Do Not Disturb' until fermentation is complete.	California Ale Yeast 82-001 American Ale 67-1056 US-05 Safale				
	During the fermentation process, CO2 will begin to escape the airlock. Follow manufacturer's pitch instructions and recommended temperature for fermentation.					
Fermenting - Primary	Once the Primary fermentation is complete, approximately 1 to 2 weeks, rack the beer into the secondary fermenter.					
Fermenting - Secondary	If the recipe calls for Dry Hops or additives that need to go into the secondary, add these now. The Scomplete within 1 to 2 weeks.	Secondary Fermentation should be				
Bottling	Siphon finished beer into a bottling bucket. If the recipe calls for any Bottling Additives to be added to now.	the bottling bucket, add them				
	At this point, follow bottling or kegging proceduresCheers!					

Adventures in Homebrewing - www.HomeBrewing.org 313 - 277 - 2739 (BREW)