%arnspirations

spark your inspiration!

BERNAT HIDE-AWAY CROCHET SOFA CADDY

SHOP KIT



MATERIALS

 Bernat® Blanket™ (10.5 oz/300 g; 220 yds/201 m)

 Sand (10014)
 2 balls or 349 yds/319 m

Size U.S. J/10 (6 mm) crochet hook **or size needed to obtain gauge.** Stitch marker. Yarn needle.

SUPER BULKY

CROCHET I SKILL LEVEL: EASY

ABBREVIATIONS

Approx = Approximately Beg = Begin(ning) Ch = Chain(s) Cont = Continue(ity) PM = Place marker

- Rem = Remain(ing) Rep = Repeat RS = Right side Sc = Single crochet Sl st = Slip stitch Sp(s) = Space(s)
- St(s) = Stitch(es) Tog = Together Tr = Treble crochet WS = Wrong side

MEASUREMENTS

Approx 15" x 33½" [38 x 85 cm], excluding fringe.

GAUGE

10 sc and 11 rows = 4" [10 cm].

INSTRUCTIONS

Notes:

- Caddy is worked with tighter gauge than standard gauge for stability.
- Caddy is worked flat in one piece and folded and seamed to form Pocket.
- Pocket is meant to hang over outer arm of sofa while Arm Wrap end folds over inner sofa arm and tucks down or is wrapped under sofa cushion to hold it firmly in place.

POCKET

Ch 36.

1st row: (RS) 1 sc in 2nd ch from hook. 1 sc in each ch to end of ch. Turn. 35 sc.

2nd row: Ch 1. 1 sc in each sc to end of row. Turn.

Rep 2nd row until work from beg measures 8" [20.5 cm] ending on a WS row. Turn.

Next row: (RS). Ch 1. *Working in back loops only*,1 sc in each sc to end of row. Turn.

PM at end of last row.

Cont with Arm Wrap as follows:

ARM WRAP

Next row: Ch 1. 1 sc in each sc to end of row. Turn. Rep last row until work from marker measures 33" [84 cm]. Fasten off.

%arnspirations™

spark your inspiration!

BERNAT HIDE-AWAY CROCHET SOFA CADDY

FINISHING

Forming and Sectioning Pocket:

With WS facing, fold Pocket along marked row to form 8" [20.5 cm] deep pocket (as shown in diagram). **Note:** WS of Arm Wrap and RS of Pocket is now facing. Join yarn with sl st to folded edge of pocket 5½" [14 cm] from left edge. Keeping yarn at back work and *working through both thicknesses*, sl st into each row to create a straight vertical chain of sl sts to upper edge of Pocket, taking care to avoid buckling work as you stitch. Fasten off.

Edging and Joining Pocket: With RS facing, join yarn with sl st to bottom right corner st of Caddy. Ch 1. Work sc evenly around 3 sides of Caddy, having 3 sc in each of top 2 corners, and *working through both thicknesses* along side edges of Pocket to join. **Do not** fasten off. Turn to work across folded bottom edge and cont with Fringe Trim as follows: **Fringe Trim: 1st row:** (RS). Ch 1. Work 37 sc evenly across folded bottom edge of Pocket working around ends of Edging row and working 1 sc in each rem loop (35 loops) along marked row (bottom edge of Pocket). Turn. 37 sc. **2nd row:** Ch 6. Skip first 3 sc. Sl st in next sc. *Ch 6. Skip next 2 sc. Sl st in next sc. Rep from * to last 3 sc. Ch 2. Skip next 2 sc. 1 tr in last

sc. Turn. **3rd row:** *Ch 6. SI st in next ch-6 sp. Rep from * to last ch-6 sp. Turn. **4th row:** Ch 6. SI st in first ch-6 sp. *Ch 6. SI st in next ch-6 sp. Rep from * to last ch-6 sp. Ch 6. SI st in tap of tr 2 rours below (2nd row)

top of tr 2 rows below (2nd row). Fasten off.

Fringe: Cut strands of yarn 12" [30.5 cm] long. Taking 3 strands tog, fold in half and knot into fringe in every ch-6 sp from last row. Trim fringe evenly.



