



# MACVOIL™

Botanical Nano Keratin Ingredient Technology

## EXTRA

### Smoothing Treatment Therapy Training Manual



[www.macvoil.com](http://www.macvoil.com)

## STEP BY STEP INSTRUCTIONS

### Before Getting Started

#### Client Consultation & Expectations

- ◆ Evaluate client's hair and discuss what to expect from the service, based on hair's curl, texture, condition and previous chemical treatments. Explain the unique safety and effectiveness of MACVOIL™ Smoothing Treatment compared with other products on the market.
- ◆ Discuss home maintenance to extend the life of the smoothing treatment.
- ◆ Quote a price for the treatment based on evaluation of the client's hair.

#### Tools & Products

You'll need the following items ready before starting the smoothing treatment:

- ◆ MACVOIL™ Smoothing Clarifying Shampoo
- ◆ MACVOIL™ EXTRA Smoothing Treatment Therapy
- ◆ MACVOIL™ Smoothing Shampoo and Re-Conditioner
- ◆ Flat Iron reaching 450 degrees
- ◆ Gloves, cape, towels, bowl, tint brush
- ◆ Heat resistant fine tooth tail comb, clips, plastic cap, blow dryer, vent brush.

### STEP 1: PREPARATION

1. Shake bottle well.
2. Pour 3/4 oz. of Smoothing Treatment Therapy into a bowl. Use more as needed. DO NOT USE more than 1 1/2 oz. of treatment. To avoid contamination. Do not return any dispensed product into original container.

#### Smoothing Clarifying Shampoo

You must properly shampoo with Smoothing Clarifying Shampoo for best results.

- ◆ Shampoo hair 2-3 times until "squeaky" clean.
- ◆ Using the clarifying shampoo ensures that all minerals and residues are thoroughly removed from hair before starting the smoothing process.
- ◆ The clarifying shampoo also lowers the pH of the hair and scalp, which allows proper adhesion of smoothing treatment and helps prevent dryness.

### STEP 2: TOWEL-DRY

Blot hair with a towel until all excess moisture is removed, still leaving the hair wet for application.

### STEP 3: APPLICATION & FLAT-IRONING

You are now ready to apply the smoothing treatment. As with all chemical services you should wear gloves during application for protection.

1. Section hair into four equal partings, start applying product at nape using 1/4" inch subsections beginning 1/4" inch from the scalp and combing through ends. Repeat for each section. **NOTE:** Evenly apply the smoothing system by "dusting" the product down the hair making sure not to oversaturate the hair.  
**IMPORTANT: DO NOT OVERSATURATE THE HAIR! THIS WILL CAUSE BUILD-UP AND AFFECT RESULTS. IF PRODUCT IS LEFT ON COMB, BRING DOWN NEXT SECTION AND COMB THROUGH TO DISTRIBUTE EXCESS PRODUCT. AVERAGE TREATMENT REQUIRES 3/4-1 1/2 OZ.**
2. Begin blow-drying the hair with a boar bristle brush under high heat until 100% dry. The boar bristle brush helps to ensure the product is distributed evenly throughout the hair.
3. Section hair into four equal partings beginning at the nape of the head, using 1/2 - 1" inch subsections and begin flat ironing section by section, making 7 to 8 passes per section. Flat iron temperature should be 400°F-450 F depending on hair type & texture and amount of smoothing desired. You should use the lowest heat setting necessary to prevent damage to the hair.
4. After treatment do not wet or wash hair for 48 hours (See customer care sheet)
5. Send client home with MACVOIL™ home maintenance system. (see below).

### HOME MAINTENANCE

Proper home maintenance using MACVOIL™ products is crucial to maintaining smoothing treatment results for 12-16 weeks. Home maintenance includes washing hair with MACVOIL™ Smoothing Shampoo and Smoothing Re-Conditioner. MACVOIL™ Argan Oil should be used for thermal styling and to extend the life of the smoothing treatment.

**WARNING:** This product contains methylene glycol. When heated it can emit trace amounts of formaldehyde. Use in well ventilated areas.