BRISA[™] Gel Enhancements Sculpted on a Form



A service option that is ideal for healthy, natural nails with a slight extension edge requiring length and design enhancement.

STEP 1:

P.R.E.P.

- 1. P Perform a manicure.
 - a. Have the client wash their hands with soap and water and towel dry.



b. Massage COOLBLUE™
 Hand Cleanser into the client's hands to cleanse skin.



 c. Remove any existing nail color from the natural nail using an acetone-based polish remover (OFFLY FAST™ Moisturizing Remover or SCRUBFRESH™ Nail Surface Cleanser) and a plastic-backed lint-free pad.



- d. If necessary, trim the length from each nail, using nail clippers.
- e. Shape the extension edge of each nail with the **240-grit side of a** Kanga™ File or Koala Buffer™.



* Dry P.R.E.P. is an excellent option for clients with great natural nails, who do not build excessive cuticle between services. Eliminating the wet cuticle treatment can shorten the service time and increase adhesion for some clients. f. Apply a small amount of

CuticleAway™ Professional

Cuticle Remover evenly around
the cuticle of each nail.*



g. Gently slide a
cuticle pusher
along the nail
plate toward the
cuticle area and
along the lateral
folds to lift and





loosen any non-living tissue from the nail plate. Remove any excess **CuticleAway™** from the nail and use a **curette** to remove non-living tissue up to the eponychium and lateral folds.

- h. Scrub nails thoroughly with soap and a damp brush, then rinse with warm water to remove the cuticle remover and soap; towel dry.*
- i. Use a manicure nipper to carefully remove any loosened, non-living tissue, as well as any loose pieces of skin or hangnails.
 Use a gentle touch during cuticle removal to protect the seals.
 Never cut living tissue as it can lead to infection.





2. R - Remove shine from the natural nail surface with the 240-grit side of the Koala Buffer™ in the direction of nail growth.



- E Eliminate surface contaminants and
 P Purify nail plate layers.
 - a. Thoroughly cleanse and temporarily dehydrate the nail plate layers with SCRUBFRESH™ using a lint-free, plastic-backed pad. Gently pull lateral folds back and scrub thoroughly to be sure all areas of the nail are completely clean.



STEP 2:

Apply Clear PERFORMANCE FORMS™

For a comprehensive tutorial of CND form application techniques see the CND^{TM} PERFORMANCE FORMS Application Step-by-Step.

 For wide nails, pre-fold the vertical perforation on each side to help shape the form.
 For small nails or dramatic C-curve, this is not necessary.



- 2. Place the form under the extension edge at a 45-degree angle and gently rock up and under the natural nail extension edge.

 Pre-tailor the form if necessary.
- **3.** Create a cylinder with the front of the form and secure the bottom tabs to create a C-curve.
- **4.** Squeeze the rear tab to secure the form. The rear "V" notch may be pinched together or opened to accommodate smaller or larger fingers.

5. Cut the tabs on the bottom of the PERFORMANCE FORMS™ to ensure proper hand placement for optimum cure.

STEP 3:

Apply BRISA™ Bond

 Apply one thin layer of BRISA™ Bond to the natural nail plate of 2-3 nails at a time ensuring that the brush has enough liquid to thoroughly and evenly cover each nail. Repeat this step until all nails are thoroughly and evenly coated.

Remember: When applying BRISA™ Bond, do not touch the skin or allow the product to flood the cuticle area.

2. Apply to five nails and cure each hand for 10 seconds (preset button 1) in the CND™ LED Lamp. Do not remove the top film after removing the nails from the lamp.



STFP 4

Create a Base Layer (optional)

This step will ensure proper adhesion and can prevent service breakdown. Implement when needed.

 Apply a thin to medium layer of BRISA™ Clear or Pure Pink - Sheer Sculpting Gel to the natural nail.



2. Apply to five nails and cure each hand for one minute (preset button 2B) in the CND™ LED Lamp.* Do not remove the top film after removing the nails from the lamp.



*If using the CND™ UV Lamp, cure for two minutes.

7 one 1 - Smile Lines

- 1. Use a string of gel to define the shape of what will become the smile line using BRISA™ Pure White or Soft White Sculpting Gel. Pick up a scoop of gel and allow a "string" to form while removing the gel from the pot. Touch the tip of the "string" to the start of the desired sidewall smile line placement on one side of the nail, and draw in the smile line with a draping motion.
- 2. Touch the brush gently to the opposite side of the sidewall to complete the line. This will "draw" in a guide for the smile line and help create consistency from nail to nail.
- 3. Once the smile line is established fill in the desired extension edge with the remaining gel on the brush.
- 4. Apply to five nails and cure each hand for one minute (preset button 2B) in the **CND™** LED Lamp.* Do not remove the top film after removing the nails from the lamp.



STEP 6:

Zones 2 & 3 -Apex, Upper Arch and Cuticle Area

- 1. Build and shape the enhancement by placing a scoop of gel onto the center of the nail in Zone 2.
- 2. Guide the product from side to side, rotating the brush at a 45-degree angle, and tapering toward the sidewalls - while keeping the bulk of the gel in the vertical center of the nail.



- 3. Gently ease the gel back toward the cuticle area lightening the touch in the middle of the nail.
- 4. Lightly feather the gel up to the established smile line.
- 5. Apply to five nails and cure each hand for one minute (preset button 2B) in the CND™ LED Lamp.* Do not remove the top film after removing the nails from the lamp.

STEP 7:

Perfect the Shape (optional)

This step will reinforce the enhancement and can prevent service breakdown. Implement when needed.

- 1. Apply a thin layer of BRISA™ Clear Sculpting Gel over the entire nail to perfect the shape.
- 2. Fill in low spots by taking a tiny scoop onto your brush. Touch the product to one side of the low spot and lift up to create a thin strand of product. Pull this strand of gel across the nail and touch to the other side. Lift off, and allow the gel to selflevel, filling in the low spot.
- 3. Apply to five nails and cure each hand for one minute (preset button 2B) in the CND™ LED Lamp.*



Shape and Define

For a comprehensive tutorial of CND finishing techniques see the Enhancement Finishing Step-by-Step.

- 1. Remove the top film with 99% Isopropyl Alcohol and a plastic-backed pad.
- 2. Remove Clear PERFORMANCE FORMS™ from the nail.



*If using the CND™ UV Lamp, cure for two minutes.

- Finish the nail using a Blizzard™
 File to define and shape.
- **4.** Smooth the surface with a **Boomerang Padded File**, making sure to remove all shine.
- Remove any dust with a disinfectable brush and a plastic-backed pad saturated with 99% Isopropyl Alcohol.

STEP 9:

Apply BRISA™ Gloss

Apply a thin layer of BRISA[™] Gloss using the CND 5 Point Polish
 Method to the extension edge
 and nail surface of all five nails
 on one hand. (For more detailed information see the CND 5 Point
 Polish Method Step-by-Step.).



 Apply to five nails and cure each hand for one minute (preset button 3) in the CND™ LED Lamp.*



- **3.** Remove the top film with **99% Isopropyl Alcohol** and a plastic-backed pad.
- Massage SOLAROIL™ Nail & Cuticle Care into the nails and skin.



PRODUCTS REQUIRED

COOLBLUE™ Hand Cleanser

OFFLY FAST™ Moisturizing Remover

CuticleAway™ Professional Cuticle Remover

SCRUBFRESH™ Nail Surface Cleanser

CND™ Files and Buffers

CND™ Clear PERFORMANCE FORMS™

CND™ ProSeries Gel Oval Brush #6

BRISA™ Bond

BRISA™ Sculpting Gels

BRISA™ Gloss

SOLAROIL™ Nail & Cuticle Care

ACCESSORIES/EQUIPMENT REQUIRED

CND™ LED Lamp

Hand towels

Hand soap

Plastic-backed, lint-free pads

Disinfectable dust brush*

99% Isopropyl Alcohol

Cuticle pusher

Manicure nippers

Nail clippers

Curette

*Optional