

Leutenegger
EST. 1891



CHAMBRAY STRIPY CUSHIONS

CHAMBRAY STRIPY CUSHION

Finished size: 50 x 50cm

MATERIALS:

- Cotton Chambray Fabrics



- 4" of Beechnut HCM008 - **A**



- 6" of Blush HCM006 - **B**



- 10" of Slate HCM011 - **C**

- 20" x 20" piece of fabric for backing
- 20" x 20" scrap fabric for inside of the cushion
- 20" x 20" piece of batting
- 50cm cushion insert

CUTTING

Cut 1 3/4in wide strips out of all of your fabric and trim down to the following sizes:



B1 = 1 3/4" x 3"

B2 = 1 3/4" x 8 1/4"

B3 = 1 3/4" x 12 1/2"

B4 = 1 3/4" x 16 1/2"

B5, B6 = 1 3/4" x 17 1/2"

B7 = 1 3/4" x 14 1/2"

B8 = 1 3/4" x 9 1/2"

B9 = 1 3/4" x 5 1/2"



A1 = 1 3/4" x 6"

A2 = 1 3/4" x 10 1/2"

A3 = 1 3/4" x 12 1/2"

A4, A5 = 1 3/4" x 13"

A5 = 1 3/4" x 12 1/2"

A7 = 1 3/4" x 7 1/2"



C1 = 1 3/4" x 3"

C2 = 1 3/4" x 8 1/4"

C3 = 1 3/4" x 12 1/2"

C4 = 1 3/4" x 16 1/2"

C5, C6 = 1 3/4" x 17 1/2"

C7 = 1 3/4" x 14 1/2"

C8 = 1 3/4" x 9 1/2"

C9 = 1 3/4" x 5 1/2"



C10 = 1 3/4" x 6"

C11 = 1 3/4" x 10 1/2"

C12 = 1 3/4" x 12 1/2"

C13, C14 = 1 3/4" x 13"

C15 = 1 3/4" x 12 1/2"

C16 = 1 3/4" x 7 1/2"

Label them as you cutting will help you with placement later. The fabric requirements is for making cushion as shown in the photograph.

© Leutenegger Pty. Ltd., 2017 For personal use only. Pattern not for resale. Items made using this pattern must not be resold.




ASSEMBLY

First assemble all of your strips into panels.

B1 to C1, B2 to C2, B3 to C3 and so on, then C10 to A1, C11 to A2 and the rest. Use an accurate 1/4" seam allowance to sew the seam.


Now it's time to start sewing panels together. Start with sewing A1/B1 and C10/A1 panels together as shown. Working from side to side, continue joining panels together.




CHAMBRAY STRIPY CUSHION

Finished size: 50 x 50cm

Alternate between the Beechnut and Blush panels as shown on diagram.



Then sew the remaining panels to each corner as shown on diagram below. These panels are intentionally a bit bigger than you need.



Finally, square up your piece to a finished 20" square

BASTING AND FINISHING

With wrong sides, layer cushion's top and scrap backing fabric, with batting in-between (quilt sandwich). Smooth out all creases and carefully baste layers together. Quilt along stitch lines as desired.

Once front of the cushion is quilted, trim off the excess scrap backing fabric and batting so that the quilted front is a square.

Pin front and back pieces together with right sides facing. Stitch around leaving opening on one side.

Insert cushion insert and slip stitch the opening. Throw that pillow on your couch and enjoy it!!