

Corn Toss- Runner

Size: 12" x 24"



Cutting *Cut from the longer side of the FQ or F8*

- **Fabric A:** Cut **Three** 2" x 5-1/2" rectangles.
- **Fabric B:** Cut **Six** 2-1/4" x 5-1/2" rectangles.
- **Fabric C:** Cut **Four** 1-1/2" strips, subcut two of them into **Two** 1-1/2" x 5-1/2" rectangles and **Two** 1-1/2" x 7-1/2" rectangles. Save 2 strips.
- **Fabric D:** Cut **One** 3" strip, subcut into **Six** 3" squares.
- **Fabric E:** Cut **Four** 2-3/4" strips.
- **Fabric F:** Cut **Four** 2-1/2" strips for binding.

Fabric Requirements

Fabric A (background 1): Fat Eight
Fabric B (background 2): Fat Eight
Fabric C (sashing): Fat Eight
Fabric D (triangles): Fat Eight
Fabric E (border): Fat Quarter
Fabric F (binding): Fat Quarter
Scraps for appliqué.
Backing: 1/2 yd.
Batting: At least a 15" x 27" piece.

Assembly

1. Prepare your backing and batting with basting spray, using fusible fleece or pins.



Find and draw center lines on the batting. Place a fabric A rectangle directly in the center of the batting horizontally, right side up and pin down.



Layer a fabric B rectangle on top of it, right sides together, aligning the raw edges. Sew through all layers and press. Add another fabric B rectangle on the other side of the fabric A rectangle and press.



2. Layer the 1-1/2" x 5-1/2" rectangle from fabric C on each side of the step 1 unit, right sides together, aligning raw edges. Sew through all layers and press. Now layer two fabric B units on top of the fabric C units, sew and press. Follow that with the two fabric A units, sew and press. Finally add the last two fabric B units and press.

3. Layer the long fabric C strips along the top and bottom of the sewn unit, right sides together, aligning the raw edges. Trim the strip to length and sew through all layers. Press. Layer the two 1-1/2" x 7-1/2" rectangles from fabric C on each short end of the sewn unit, right sides together and sew through all layers. Press.



4. Repeat the process in step 3 with the unit 3 strips border strips. Layer two strips on the longer sides of the sewn unit, sew and press. Trim off the excess fabrics on each side. Repeat with the short sides of the runner. Trim the backing and batting to the same size as the sewn top.



5. Take the 3" fabric D squares and fold them in half, corner to corner to form a triangle, with wrong sides together as shown. Press. Then refold them into a smaller triangle so that the raw edges are all together and press.



6. Arrange 3 triangles along two edges of the runner (I did the upper right short side and bottom left long side) and pin down. Let the tips of the triangles overlap about a 1/4". Now sew the binding to the runner, catching the triangles in the seam.



7. Add the Candy Corn appliques according to the general instructions. Finish the edges by machine through all layers.

