



Get Wrecked Noob! Imperial Pilsner (Ale Version)



For today's lesson, open your textbooks to page 1: How to Spot a Noob 101. In the noob's natural habitat, you will witness this curious creature performing a variety of common tasks while employing extraordinary levels of ridiculousness, such as stirring a can of paint with a pair of pliers, changing the car's oil with antifreeze, and staring straight into a clogged toilet after tossing in a cherry bomb. You will also witness the noob chugging down an entire frosty liter of this delicious Imperial Pilsner, but at 8.2% alcohol, we will now witness our poor noob slurring his speech, stumbling a zigzag line and falling backwards behind the couch, where he will slumber peacefully until morning. Of course, we can't fault the noob's great taste, because this hearty brew is rich and complex, with a luxurious malt character deftly balanced with smooth bitterness and the delightfully long finish of floral and spicy hops, which goes down with remarkable ease and thus explains our noob behind the couch. So remember: don't look down on our beloved noobs, because these inexperienced buffoons have been providing us an endless source of entertainment and helping to make us all look better since the beginning of time.

Just the Facts, Ma'am:

Beer Style: Imperial Pilsner (Ale Version)
 Original Specific Gravity: 1.074 - 1.078
 Final Specific Gravity: 1.012 - 1.016
 Alcohol by Volume: 8.2%
 Color: 6 SRM (Deep Golden)
 International Bittering Units: 57
 Time to Awesome Drinkability: 7 Weeks!

Your recipe kit includes the freshest malt, hops and yeast. If you are not going to brew your recipe immediately, it is important to refrigerate your yeast and hops. If your recipe includes bags of malt syrup, these should be refrigerated too. Bags of dried malt do not require refrigeration. Also, all grains are best stored at dry room temperature.

Ingredients:

Fermentables:

8.8 lbs Pilsen Light Malt Extract Syrup
 2 lbs Dextrose

Hops:

½ oz Polaris Hops (Bittering, 65 Minutes)
 ½ oz Sterling Hops Bittering, 65 Minutes)
 ¼ oz Crystal Hops (Flavor & Aroma, 15 Minutes)
 1 oz Saaz Hops (Flavor & Aroma Hop, After-the-Boil Steep, 10 Minutes)
 ¾ oz Crystal Hops (Flavor & Aroma Hop, After-the-Boil Steep, 10 Minutes)
 ½ oz Sterling Hops (Flavor & Aroma Hop, After-the-Boil Steep, 10 Minutes)

Yeast:

Liquid Yeast: Wyeast 1056 American Ale Yeast

Or

Dry Yeast: Omega Dried LUTRA Kveik or Safale US-05 Dried Ale Yeast

Brewing Supplies & Flavors:

Optional: 1 oz of Lemon, Lime, Curacao Orange, Sweet Orange or Grapefruit Peel (In Spice Potion)
 5 oz Priming Sugar

Brew Day Checklist:

On brew day, you will require the following equipment:

- Brew Pot - A 5 gallon brew pot is ideal, but never use a pot that is less than 4 gallons.
- Large measuring cup - 4 cup (32 oz) capacity
- Long-handled spoon or paddle for stirring the boiling wort.
- Primary Fermenter - A 6½ gallon (or greater) food-grade plastic bucket with lid, or a 6½ glass carboy.
- Airlock

- Stopper (if using a carboy)
- Funnel (if using a carboy)
- Hydrometer (Optional, if you want to measure your specific gravity)
- Sanitizing Solution
- Scissors
- Siphon Setup
- Blow-Off Tube (Recommended)

If you choose to rack the beer into the secondary fermenter, you will require the following equipment:

- 5 gallon carboy
- Airlock
- Stopper

Preparation of the Spice Potion (Optional)

On brew day, place your chosen fruit peel in a jar with 1 cup of vodka. Screw on a tight fitting lid and let the spices soak in the vodka until one day before bottling the beer.

Note: Don't hesitate to use the least expensive "rot-gut" vodka you can find. The quality of vodka has no effect on the final quality of the spice potion.

The Magical Procedure:

Liquid Yeast Activation Before Brewing:

If you are fermenting with liquid yeast, you must activate the yeast packet before it is ready to pitch. Always check the manufacturing date stamped on the yeast packet. Yeast that is less than 1 month old may be activated on brew day. A yeast that is more than 2 months old may require additional preparation time. Always make sure your yeast has been properly activated before using. For more information about yeast starters, please visit the 'Frequently Asked Questions' section on boomchugalug.com.

Time to Brew!

Total Boiling Time: 65 Minutes. While your wort is boiling, you should sanitize your fermentation equipment, such as your primary fermenter, airlock, scissors, stopper, etc. After you have sanitized your fermenter, fill it with 2 gallons of cold water, into which you will later add your hot boiled wort.


Note 1: This recipe has malt syrup additions at two different times during the boil. Please read all of the instructions before beginning.

Note 2: Before beginning the recipe, divide out the required hop quantities for each scheduled addition. To measure ¼ oz of hops, simply divide each 1 oz bag into two equal halves. Then take half of the half. This accuracy is adequate for brewing this recipe.

1. Add to 2½ gallons of water to your brew kettle, and bring this water to a boil. Measure this volume carefully to ensure you extract the proper amount of hop bitterness.
2. When the water begins boiling, remove the pot from the heat and add 4 cups of malt extract syrup (See Note 3 below). To prevent scorching, stir until all of the malt is dissolved. Then bring this mixture to a boil. Watch for boilovers!

Boomchugalug.com

Flip the sheet to continue the magic. Also, this is a good time to pour a cold one! →



Get Wrecked Noob! Imperial Pilsner

Page 2....Wow, this is good stuff. I wish there could be more!

Note 3: Measuring 4 cups (32 fluid ounces) of malt syrup is easy! Make sure you use a measuring cup that holds at least 4 cups (32 fluid ounces). With scissors, cut off a SMALL corner of the malt syrup bag and then slowly squeeze the 4 cups of syrup into the measuring cup. If you are a little over or under, it's no problem. Before you add this malt syrup to your brew pot in Step 2, you may soften it by placing the measuring cup in the microwave and warming it for 30 seconds. Also, before Step 4, be sure to store the opened bag of syrup in an upright position (duh!). We find that propping it upright in a round plastic food storage container (like a Tupperware) to be the easiest.

3. When boiling begins, add ½ oz each of Polaris and Sterling hops and ¼ oz of Crystal hops. Boil these hops for the entire 65 minutes.
4. With 5 minutes remaining in the 65 minute boil, pause the brew timer and remove the kettle from the heat. Add the remaining malt extract syrup and 2 lbs dextrose. Stir until dissolved, bring the wort back to a boil, and boil for the last 5 minutes.
5. At the end of the 65 minute boil, remove kettle from the heat. This recipe uses a 10 minute after-the-boil hop addition. Brewers often call this the "whirlpool hop addition" because you stir the hops into the hot wort. Add ½ oz of Sterling hops, ¾ oz of Crystal hops and 1 oz of Saaz Hops. Place cover over kettle and steep for 10 minutes before cooling the wort.

Note: during this steep, it is important to cover the kettle to prevent loss of the delicate and volatile hop oils.

Chill out, Man! (Chill the Wort)

1. At the end of the 10 whirlpool, cool the wort to approximately 75°F as quickly as possible. With extract brewing, the easiest way to quick-chill the wort is to place your brew pot into a sink full of ice. For more information about cooling your wort quickly, please see 'Fast Wort Chilling' in the 'Frequently Asked Questions' section on our website.
2. Add your chilled wort to the 2 gallons of water already in your fermenter.
3. Add any extra water needed to bring the total volume in your fermenter to 5 gallons.
4. If you would like to measure the specific gravity, now is a good time. To get an accurate reading, it is important to make sure all of the heavy wort extract you added to the fermenter has been completely mixed in the water.

Pitch the Yeast! (Into the Wort, But Not Out the Window!)

1. When your wort has cooled to about 75°F (70° - 78°F is okay), aerate the wort before adding the yeast. Simply close the fermenter and swirl around to mix in oxygen. If you are swirling a carboy, it is helpful to place the carboy on a thick, folded blanket to avoid damaging the vessel.
2. After aerating, pitch (add) the yeast. Use the sanitized scissors to cut open the yeast packet. If you are using liquid yeast, sanitize the pack before opening. If you are using dried yeast, simply sprinkle the yeast over the wort. No mixing is necessary with dried yeast.
3. Close the fermenter, attach the airlock, and keep the fermenter warm (between 70° - 78°F) until you see fermentation beginning, such as the airlock bubbling once every 30 seconds. Wrapping the fermenter with a blanket is an easy way to keep the fermenter warm.

Primary Fermentation:

There are several ways to know when fermentation has begun. First, you will begin to see bubbling through the airlock. If you are using a carboy, then you will usually see the yeast begin to form a layer over the beer's surface.

1. Once fermentation begins, move the fermenter to a room with the proper temperature. The ideal temperature to ferment this beer is between 62° - 73°F. Do not let the temperature drop below the minimum specified temperature. If you do, fermentation may stop too soon. That's a bummer, man.

2. Active fermentation may take as long as two weeks after pitching the yeast, although fermentation may finish in 3 to 5 days.
3. If you choose to siphon the beer to secondary carboy for additional clearing and maturation, do so when fermentation begins to slow. If you will not be using a secondary, allow fermentation to complete in the primary fermenter.
4. (Optional) Add the spice potion. On the day before bottling, add the spice potion to the fermenter: Shake the spice potion thoroughly to break up the sediment and dump in all of the liquid and chunky goodness. No need to stir - the flavors will mix naturally on their own. The chunky spices will settle to the bottom of the fermenter and will be left behind later when you siphon the beer to the bottling bucket.

Time to Bottle!

There are several ways to tell when fermentation is complete (besides your drooling). If you correctly pitched the yeast and fermentation quickly began, and if the beer fermented vigorously and the fermenter was always within the correct temperature range (62° - 73°F), then fermentation should finish in two weeks or less. You should see virtually no activity in the airlock. For example, if the airlock only bubbles once a minute or longer, then fermentation should be complete. If you are unsure if fermentation has ended, you may use your hydrometer to measure the specific gravity. If your specific gravity does not change after two or more days, then fermentation is complete and you are ready to bottle!

1. Before bottling, sanitize your bottling bucket, auto siphon (or racking cane), hose, bottle filler, caps and bottles. Glass bottles may be sanitized one day in advance by baking them in the oven. More information about baking your bottles can be found under 'Baking Beer Bottles' in the 'Frequently Asked Questions' section on our website.
2. Dissolve 5 ounces (weight) or ¾ cup of priming sugar (dextrose / corn sugar) in 16 oz water. Boil for 5 minutes.
3. Pour the sugar solution into the bottling bucket, and siphon in the beer. Siphon carefully, trying to minimize splashing and aeration of the beer. Also when siphoning, be sure to leave behind the sediment at the bottom of the fermenter. When done siphoning, gently stir the beer in the bucket to make sure all of the sugar solution has been dissolved. Your racking cane makes a convenient stirring wand.
4. Elevate your bottling bucket, and attach your siphon hose and bottle filler to the bucket's spigot. Fill the bottles to about 1 inch from the top, and cap each bottle.

Carbonation and Maturation!

Now that your bottles are primed and capped, the remaining yeast will undergo a second fermentation in the bottle whereby they eat the priming sugar and produce carbon dioxide, which is trapped in the bottle to produce the carbonation. While your beer is carbonating, it will also be clearing and maturing - the young, rough undeveloped flavors develop into your magical beverage! Your wondrous elixir reaches awesome drinkability about 10 weeks from the day you began the brew, but don't be surprised if it keeps getting better as time goes on.

1. Place your bottles in a dark place at room temperature (65°F - 80°F), and wait at least two weeks for the beer to carbonate. It is important that you keep the beer between 65°F - 80°F for carbonation to develop. If the beer cools below 65°F, it may not properly carbonate. In brewing, this is officially known as the buzzkill. Keep it warm, let it carbonate!
2. Get your bottle opener handy dude (or dudette), because it's time to drink a beer! When pouring the beer into your glass, be sure to leave the bottle's sediment behind. That sediment is the yeast which carbonated your beer, and if you pour it into your glass, you'll make the beer cloudy and taste yeasty.
3. Once your beer is carbonated, you may store it in a cool place. Keep in mind that home-brewed is unfiltered, and unfiltered beers actually continue to improve with time. If your beer seems rough-around-the-edges or tastes yeasty, these qualities usually morph into a smooth, clean beer over time. Cheers!

Boomchugalug.com