

## Keep On Keepin' On Session IPA



You're a hop junkie on a heroic mission to survive the long haul, and whether its a day on the beach, in the boat or on the slopes, you want that slow-release of good taste so you can spend more quality-time bonding with your dear friends like Apollo, Azacca, Citra, Galaxy, Mosaic and Ella. And God gave you two hands for what reason? To grab two pints, of course! So pour yourself a couple of cold ones and let the velvety malts and balanced bitterness fade into the hop detonation of fruit flavors like apricot, citrus, mango, peach, and passion fruit that will blow your mind with epic drinkability to help you keep on keepin' on!

### Just the Facts, Ma'am:

BJCP Style: 21A. American IPA

Original Specific Gravity: 1.043 - 1.047 Final Specific Gravity: 1.007 - 1.011

Alcohol by Volume: 4.7%

Color: 6 SRM (Keepin' On the Golden!)

International Bittering Units: 42

Time to Awesome Drinkability: 4 Weeks!

Your recipe kit includes the freshest malt, hops and yeast. If you are not going to brew your recipe immediately, it is important to refrigerate your yeast and hops. If your recipe includes bags of malt syrup, these should be refrigerated too. Bags of dried malt do not require refrigeration. Also, all grains are best stored at dry room temperature.

### Ingredients:

Fermentables:

5.7 lbs. Extra Light Malt Extract Syrup

Grains & Wort Additives:

8 oz Cara Blonde Malt (Crushed)

6 oz Honey Malt (Crushed)

Hops:

½ oz Apollo Hops (Bittering, 50 Minutes)

½ oz Apollo Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

½ oz Azacca Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

1/4 oz Citra Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

1/4 oz Galaxy Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

½ oz Mosaic Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

½ oz Perle Hops (Flavor & Aroma Hop, Whirlpool, 30 Minutes)

½ oz Azacca Hops (Dry Hop, Flavor & Aroma)

3/4 oz Citra Hops (Dry Hop, Flavor & Aroma)

3/4 oz Galaxy Hops (Dry Hop, Flavor & Aroma)

½ oz Mosaic Hops (Dry Hop, Flavor & Aroma)

½ oz Perle Hops (Dry Hop, Flavor & Aroma)

Yeast:

Liquid Yeast: Wyeast 1318 London III Ale Yeast

0

Dry Yeast: Safale S-04 Yeast OR Lallemand Verdant IPA Yeast

Brewing Supplies & Flavors:

1 Muslin Bag

5 oz Priming Sugar

### **Brew Day Checklist:**

On brew day, you will require the following equipment:

Brew Pot - A 5 gallon brew pot is ideal, but never use a pot that is less than 4 gallons.

///

- Long-handled spoon or paddle for stirring the boiling wort.
- Primary Fermenter A 6½ gallon (or greater) food-grade plastic bucket with lid, or a 6½ glass carboy.
- Airlock
- Stopper (if using a carboy)
- Funnel (if using a carboy)
- · Hydrometer (Optional, if you want to measure your specific gravity)
- · Sanitizing Solution
- · Scissors
- · Siphon Setup

On the day you rack the beer into the secondary fermenter, you will require the following equipment:

- 5 gallon carboy
- Stopper
- Airlock
- Siphon Setup

### The Magical Procedure:

### Liquid Yeast Activation Before Brewing:

If you are fermenting with liquid yeast, you must activate the yeast packet before it is ready to pitch. Always check the manufacturing date stamped on the yeast packet. Yeast that is less than 1 month old may be activated on brew day. A yeast that is more than 2 months old may require additional preparation time. Always make sure your yeast has been properly activated before using. For more information about yeast starters, please visit the 'Frequently Asked Questions' section on boomchugalug.com.

### Time to Brew!

Total Boiling Time: 50 Minutes. While your wort is boiling, you should sanitize your fermentation equipment, such as your primary fermenter, airlock, scissors, stopper, etc. After you have sanitized your fermenter, fill it with 2 gallons of cold water, into which you will later add your hot boiled wort.

Note 1: This recipe has malt syrup additions at two different times during the boil. Please read all of the instructions before beginning.

- Note 2: This recipe uses three different hop additions. Before beginning the recipe, divide out the required hop quantities for each scheduled addition. To measure ¼ oz of hops, simply divide each 1 oz bag into two equal halves. Then take half of the half. This accuracy is adequate for brewing this recipe.
- Place the crushed grains in the muslin bag and add to 2½ gallons of water. Measure
  the water volume carefully to ensure you extract the proper amount of hop bitterness
  during the boil.
- Heat water until the temperature is between 150° and 170°F. Steep the grains between this temperature range for 30 minutes. Steeping longer than 30 minutes does not hurt.
- Remove and discard the grains. Add <u>2 cups</u> of malt extract syrup (See note below).
   To prevent scorching, stir until all of the malt is dissolved. Then bring this mixture to a boil. Watch for boilovers!

Note: Measuring 2 cups (16 fluid ounces) of malt syrup is easy! Make sure you use a measuring cup that holds at least 2 cups (16 fluid ounces). With scissors, cut off a SMALL corner of the malt syrup bag and then slowly squeeze the 2 cups of syrup into the measuring cup. If you are a little over or under, it's no problem. Before you add this malt syrup to your brew pot in Step 3, you may soften it by placing the

Boomchugalug.com

Flip the sheet to continue the magic. Also, this is a good time to pour a cold one!



# Keep On Keepin' On Session IPA



Page 2.... Wow, this is good stuff. I wish there could be more!

Boil Hops		Whirlpool Hops		Dry Hop	
Apollo	½ oz	Apollo	½ oz	Azacca	½ oz
		Azacca	½ oz	Citra	3/4 OZ
		Citra	1/4 OZ	Galaxy	3/4 OZ
		Galaxy	1/4 OZ	Mosaic	½ oz
		Mosaic	½ oz	Perle	½ oz
		Perle	½ oz		

measuring cup in the microwave and warming it for 30 seconds. Also, before Step 5, be sure to store the opened bag of syrup in an upright position (duh!). We find that propping it upright in a round plastic food storage container (like a Tuppeware) to be 2. Allow the beer to rest in the secondary for 1 - 2 weeks before bottling.

- 4. When boiling begins, add the Boil Hops as listed in the table above. Boil these hops for the entire 65 minutes. During this boil time, take note of the approximate starting volume in the brew pot. As the boil progresses, try to maintain this approximate starting volume by adding additional boiling water to the kettle to make up for this volume lost to
- With 5 minutes remaining in the 65 minute boil, pause the brew timer and remove the kettle from the heat. Add the remaining malt extract syrup. Stir until dissolved, bring the wort back to a boil, and boil for the last 5 minutes.
- At the end of the 65 minute boil, remove kettle from the heat. This recipe uses a 30 Time to Bottle! minute after-the-boil hop addition. Brewers often call this the "whirlpool hop addition" because you stir the hops into the hot wort.

Add the hops to your brew kettle shown in the Whirlpool Hops table above. Stir well. Place the cover over kettle and steep with the heat off for 30 minutes.

Note: during this steep, it is important to cover the kettle to prevent loss of the delicate and volatile hop oils.

## Chill out, Man! (Chill the Wort)

- 1. At the end of the 50 minute boil, cool the wort to approximately 75°F as quickly as possible. With extract brewing, the easiest way to quick-chill the wort is to place your brew pot into a sink full of ice. For more information about cooling your wort quickly, please see 'Fast Wort Chilling' in the 'Frequently Asked Questions' section on our
- 2. Add your chilled wort to the 2 gallons of water already in your fermenter.
- 3. Add any extra water needed to bring the total volume in your fermenter to 5 gallons.
- reading, it is important to make sure all of the heavy wort extract you added to the fermenter has been completely mixed in the water.

### Pitch the Yeast! (Into the Wort, But Not Out the Window!)

- 1. When your wort has cooled to 75°F (70° 78°F is okay), aerate the wort before adding the yeast. Simply close the fermenter and swirl around to mix in oxygen. If you are swirling a carboy, it is helpful to place the carboy on a thick, folded blanket to avoid 4. damaging the vessel.
- 2. After aerating, pitch (add) the yeast. Use the sanitized scissors to cut open the yeast packet. If you are using liquid yeast, sanitize the pack before opening. If you are using Carbonation and Maturation! dried yeast, simply sprinkle the yeast over the wort. No mixing is necessary with dried
- Close the fermenter, attach the airlock, and keep the fermenter warm (between 70° -78°F) until you see fermentation beginning, such as the airlock bubbling once every 30 seconds. Wrapping the fermenter with a blanket is an easy way to keep the fermenter

### Primary Fermentation:

There are several ways to know when fermentation has begun. First, you will begin to see bubbling through the airlock. If you are using a carboy, then you will usually see the yeast begin to form a layer over the beer's surface.

1. Once fermentation begins, move the fermenter to a room with the proper temperature. The ideal temperature to ferment this beer is between 60° - 72°F. Do not let the 2. Once your beer is carbonated, you may store it in a cool place. Unfiltered home-brew temperature drop below 60°F. If you do, fermentation may stop too soon. That's a bummer, man.

2. Active fermentation may take as long as two weeks after pitching the yeast, although fermentation may finish in 3 to 5 days.

### Secondary Fermentation:

After about one week, fermentation will begin to slow. This is a good time to siphon the beer into the 5 gallon glass carboy.

- 1. Dry Hop: When siphoning your beer into the secondary, add the hops listed in the Dry Hop table above. when racking into the secondary carboy. Just cut 'em open and dump 'em in. Dude, that was easy!

Note: if your brewing equipment does not include a 5 gallon carboy (secondary fermenter), then simply add the dry hops to your primary fermenter and allow the beer to age with the hops for approximately 7 days before bottling the beer. If you choose to dry hop in the primary fermenter, you will notice that a lot of the hops will float on the beer's surface. After a few days of dry hopping, it is useful to stir the beer's surface to help the floating hops settle to the bottom of the fermenter. This will make siphoning the beer much easier and cleaner at bottling time. If you choose to stir down the floating hops, be sure to use a properly sanitized long spoon!

There a several ways to tell when fermentation is complete (besides your drooling). If you correctly pitched the yeast and fermentation quickly began, and if the beer fermented vigorously and the fermenter was always within the correct temperature range (60° -72°F), then fermentation should finish in two weeks or less. You should see virtually no activity in the airlock. For example, if the airlock only bubbles once a minute or longer, then fermentation should be complete. If you are unsure if fermentation has ended, you may use your hydrometer to measure the specific gravity. If your specific gravity does not change after two or more days, then fermentation is complete and you are ready to

- 1. Before bottling, sanitize your bottling bucket, auto siphon (or racking cane), hose, bottle filler, caps and bottles. Glass bottles may be sanitized one day in advance by baking them in the oven. More information about baking your bottles can be found under 'Baking Beer Bottles' in the 'Frequently Asked Questions' section on our
- 4. If you would like to measure the specific gravity, now is a good time. To get an accurate 2. Dissolve 5 ounces (weight) or 3/4 cup of priming sugar (dextrose / corn sugar) in 16 oz water. Boil for 5 minutes.
  - 3. Pour the sugar solution into the bottling bucket, and siphon in the beer. Siphon carefully, trying to minimize splashing and aeration of the beer. Also when siphoning, be sure to leave behind the sediment at the bottom of the fermenter. When done siphoning, gently stir the beer in the bucket to make sure all of the sugar solution has been dissolved. Your racking cane makes a convenient stirring wand.
  - Elevate your bottling bucket, and attach your siphon hose and bottle filler to the bucket's spigot. Fill the bottles to about 1 inch from the top, and cap each bottle.

Now that your bottles are primed and capped, the remaining yeast will undergo a second fermentation in the bottle whereby they eat the priming sugar and produce carbon dioxide, which is trapped in the bottle to produce the carbonation. While your beer is carbonating, it will also be clearing and maturing - the young, rough undeveloped flavors develop into your magical beverage! Your wondrous elixir reaches awesome drinkability about 6 weeks from the day you began the brew, but don't be surprised if it keeps getting better as time goes on.

- 1. Place your bottles in a dark place at room temperature (62°F-75°F), and wait at least two weeks for the beer to carbonate. It is important to keep the beer between 62°F -75°F for carbonation to develop. If the beer cools below 62°F, it may not properly carbonate. In brewing, this is officially known as the buzzkill. Keep it warm, let it carbonate!
- is unfiltered, and unfiltered beers will improve with time. If your young beer is rough or yeasty, these flavors will mellow over time. Cheers!

