



Pandemonium Porter



Page 2....Wow, this is good stuff. I wish there could be more!

1. Place all grains in the large muslin bag and add to 2¼ gallons of water. Measure the water volume carefully to ensure you extract the proper amount of hop bitterness during the boil.
2. Heat water until the temperature is between 150° and 170°F. Steep the grains between this temperature range for 30 minutes. Steeping longer than 30 minutes does not hurt.
3. Remove and discard the grains, and bring this mixture to a boil. Remove the pot from the heat and add malt extract, lactose, and brown sugar. To prevent scorching, stir until all of the malt is dissolved. Then bring this mixture to a boil. Watch for boilovers!
4. When boiling begins again, add 1 oz of Nugget hops. Boil for 60 minutes.
5. While the wort is boiling, prepare the coffee. With the ground coffee beans, make two pots (96 oz) of coffee from an automatic-drip coffee maker. Add this coffee during Step 7.
6. With 5 minutes remaining in the 60 minute boil, add the baker's chocolate.
7. With 1 minute remaining in the 60 minute boil, add the coffee to the brew pot.

Chill out, Man! (Chill the Wort)

1. At the end of the 60 minute boil, cool the wort to approximately 75°F as quickly as possible. With extract brewing, the easiest way to quick-chill the wort is to place your brew pot into a sink full of ice. For more information about cooling your wort quickly, please see 'Fast Wort Chilling' in the 'Frequently Asked Questions' section on our website.
2. Add your chilled wort to the 2 gallons of water already in your fermenter.
3. Add any extra water needed to bring the total volume in your fermenter to 5½ gallons.
4. If you would like to measure the specific gravity, now is a good time. To get an accurate reading, it is important to make sure all of the heavy wort extract you added to the fermenter has been completely mixed in the water.

Pitch the Yeast! (Into the Wort, But Not Out the Window!)

1. When your wort has cooled to approximately 75°F (70° - 78°F is okay), aerate the wort before adding the yeast. Simply close the fermenter and swirl around to mix in oxygen. If you are swirling a carboy, it is helpful to place the carboy on a thick, folded blanket to avoid damaging the vessel.
2. After aerating, pitch (add) the yeast. Use the sanitized scissors to cut open the yeast packet. If you are using liquid yeast, sanitize the pack before opening. If you are using dried yeast, simply sprinkle the yeast over the wort. No mixing is necessary.
3. Close the fermenter, attach the airlock, and keep the fermenter warm (between 70° - 78°F) until you see fermentation beginning, such as the airlock bubbling once every 30 seconds. Wrapping the fermenter with a blanket is an easy way to keep the fermenter warm.

Fermentation:

There are several ways to know when fermentation has begun. First, you will begin to see bubbling through the airlock. If you are using a carboy, then you will usually see the yeast begin to form a layer over the beer's surface.

1. Once fermentation begins, move the fermenter to a room with the proper temperature. The ideal temperature to ferment this beer is between 64° - 74°F. Do not let the temperature drop below 64°F. If you do, fermentation may stop too soon. That's a bummer, man.

Note: Very little if any krausen foam will appear on the surface of the fermenting beer. This is due to the presence of oily cocoa butter from the chocolate, which is floating on the surface. Do not be concerned. When racking the fermented beer into the secondary carboy, siphon below the floating layer of cocoa butter, being careful to leave the oily top layer in the fermenter. Then, when racking from the secondary fermenter into the bottling bucket, be careful again to leave behind any remaining cocoa butter floating on the surface. These two combined rackings should remove any residual cocoa butter from the final beer.

2. Active fermentation may take as long as two weeks after pitching the yeast, although fermentation may finish in 3 to 5 days.

Secondary Fermentation:

After about one week, fermentation will begin to slow. This is a good time to siphon the beer into the 5 gallon glass carboy. If you will not be using a secondary, allow fermentation to complete in the primary fermenter.

Time to Bottle!

There are several ways to tell when fermentation is complete (besides your drooling). If you correctly pitched the yeast and fermentation quickly began, and if the beer fermented vigorously and the fermenter was always within the correct temperature range (64° - 74°F), then fermentation should finish in two weeks or less. You should see virtually no activity in the airlock. For example, if the airlock only bubbles once a minute or longer, then fermentation should be complete. If you are unsure if fermentation has ended, you may use your hydrometer to measure the specific gravity. If your specific gravity does not change after two or more days, then fermentation is complete and you are ready to bottle!

1. Before bottling, sanitize your bottling bucket, auto siphon (or racking cane), hose, bottle filler, caps and bottles. Glass bottles may be sanitized one day in advance by baking them in the oven. More information about baking your bottles can be found under 'Baking Beer Bottles' in the 'Frequently Asked Questions' section on our website.
2. Dissolve 5 ounces (by weight) or 3/4 cup of corn sugar in a 16 oz of water. Boil for 5 minutes. Corn sugar is sometimes called dextrose or priming sugar.
3. Place your fermenter on the counter and your bottling bucket on the floor. Pour the sugar solution into the bottling bucket, and siphon the beer from the fermenter into the bottling bucket. Siphon carefully, trying to minimize splashing and aeration of the beer. Also when siphoning, be sure to leave behind the sediment at the bottom of the fermenter. There's no problem if you should siphon up a little sediment. When you're done siphoning, gently stir the beer in the bottling bucket to make sure all of the sugar solution has been dissolved. Your racking cane makes a convenient stirring wand.
4. Place your bottling bucket on the counter, and attach your siphon hose and bottle filler to the bucket's spigot. Fill the bottles to about 1 inch from the top, and cap each bottle.

Carbonation and Maturation!

Now that your bottles are primed and capped, the remaining yeast will undergo a second fermentation in the bottle whereby they eat the priming sugar and produce carbon dioxide, which is trapped in the bottle to produce the carbonation. While your beer is carbonating, it will also be clearing and maturing - the young, rough undeveloped flavors develop into your magical beverage! Your wondrous elixir reaches awesome drinkability about 6 weeks from the day you began the brew, but don't be surprised if it keeps getting better as time goes on.

1. Place your bottles in a dark place at room temperature (62° F - 75° F), and wait at least two weeks for the beer to carbonate. It is important that you keep the beer between 62° F - 75° F for carbonation to develop. If the beer cools below 62° F, it may not properly carbonate. In brewing, this is officially known as the buzzkill. Keep it warm, let it carbonate!
2. Get your bottle opener handy dude (or dudette), because it's time to drink a beer! When pouring the beer into your glass, be sure to leave the bottle's sediment behind. That sediment is the yeast which carbonated your beer, and if you pour it into your glass, you'll make the beer cloudy and taste yeasty. But this is a ripoff, you say! I'm losing a 1/4 inch of my wonderful beer! If you'd like to do so (and we most certainly do!), you may swirl up and drink the dregs. Brewer's yeast is a rich source of vitamin B complex, so here's to your health!
3. Once your beer is carbonated, you may store it in a cool place. Keep in mind that home-brewed is unfiltered, and unfiltered beers actually continue to improve with time. If your beer seems rough-around-the edges or tastes yeasty, these qualities usually morph into a smooth, clean beer over time. Cheers!



Boomchugalug.com

