

# Accidental **DUNK**

*Red Rye Ale – 5.5 Gal - OG 1.048 – FG 1.010 – ABV 5.0% - IBU 23 – SRM 12*

This is a tale of two men. One who has been trying to make the perfect Dunkelweizen, and another who is only interested in extinct beer styles. For the last 18 months or so Jeremy has been attempting to make a Dunkelweizen that is “Beer of the Month” worthy. A Dunkelweizen for those that don’t know is a “dark” wheat beer. Its more malt forward and is distinguished by its malty sweetness. We have made a number of Dunkelweizens and all have been failures. Too acidic, too sweet, too dark, etc. It is quite simply Jeremy’s white whale.

Enter young William, our newest team member and 100% the nerdiest beer lover we have ever met. He LOVES to talk about and brew beer styles that have gone extinct. There are all sorts of beer styles he wants to expose us too, the first one is the Roggenbier. Roggenbier’s are rye beers made with at least 50% rye malt and fermented with traditional hefeweizen yeast. He did the research and came up with a recipe. Jeremy & Will brewed it together, packaged it, and then tasted it. And wouldn’t you know, this beer tastes JUST like the white whale Dunkelweizen that Jeremy has been trying to make for years. A beer with zero wheat malt ends up tasting remarkably like a dark wheat beer – go figure. The important part is that it is delicious, and both Jeremy and Will are thrilled with the result.

This beer has one of the most viscous pours we have ever seen. The rye malt adds a decadent thickness to the beer along with a spicy and smooth profile. The Red X and Special X add colour and a sweet malt profile, and the 23 IBU’s balances out the sweetness to make it nice and approachable.

**Brewing Notes:** *The mash could be sticky with all the Rye malt in the mash. Especially if you are using a mash tun. Brew in a Bag setups should fare better here. If you are worried about a stuck mash, then we recommend adding rice hulls during the mashing process.*

## Ingredients

Grains	Amount (lbs)	
Rye Malt	5	
Red X	4	
Caramunich Type 3	0.4	
Special X	0.1	
Carared	0.4	
Yeast Lightning	1 gram (1/4 tsp)	
Hops	Amount (oz)	Boil Schedule (minutes)
Magnum	0.5	45
Saaz	1.0	10
Yeast		
Weizen 1 – Escarpment Labs	1 Package	
Extras – Sold Separately		
Irish Moss	1 tsp for last 15 minutes of boil	
DME/Dextrose	150g (1/2 cup) at bottling for priming	

## Important Tips on Brewing

- Be extra cautious when it comes to cleaning! Once you have stopped boiling your wort everything that gets in contact with the beer MUST be sanitary.
- The temperature of your mash is ABSOLUTELY CRITICAL. Not being in the 150-155f range can drastically affect your beer. Make sure you correct the temperature ASAP once all the grain has been added to the mash.
- Always let your beer ferment for 10 days! Do not disturb it, do not open the lid. It is absolutely natural for the airlock to stop bubbling after a few days, it is still fermenting though.
- Oxidization: Airspace is always something to consider. When undergoing primary fermentation airspace is needed so that the beer can bubble up and ferment vigoursley without leaking out of the container. The fermentation creates a layer of CO2 that remains in the pail due to the airlock. Once primary fermentation is over, and the lid has been opened, the layer of CO2 dissipates, and oxygen replaces it. At this point airspace can ruin your beer. When racking into carboys make sure they are filled to the top, or you blast CO2 inside to prevent oxidization. Ask us for details on this!
- Before bottling, make sure you use a priming calculator (many can be found online) to verify the amount of sugar that needs to be added.

## Instructions

Mashing -> converting the grain into a fermentable liquid.

- 1) Bring 6 gallons of water in your brew pot to 155°F. This is our strike temperature. Turn off the heat to the pot.
- 2) Wrap the muslin/nylon bag around the brew pot and slowly pour all the milled grains into the bag. Stir them in while adding to prevent clumps. The addition of grain should drop the temperature down to 150-155°F.
- 3) We want to mash the grain at 153°F for 60 minutes. It is very important to hold the temperature at 153°F. If the temperature rises above 155°F it hurts the fermentation, or if it dips below 149°F it can lead to a thinner tasting beer.
  - a. The first 15-30 minutes are essential for the success of your brew. The temperature HAS TO BE IN THE RANGE OF 150-155°F. Sometimes adding the grain to the strike water does not lower the temperature enough, in this case add a little bit of cold water to bring the temperature down. Cover the pot with your lid and let it sit.
  - b. Most brew pots will be able to maintain 153°F without adding heat for 20 minutes, we recommend checking the temperature every 15 minutes, and if it drops add more heat to bring it up. We recommend opening the lid and using a thermometer in the liquid.
- 4) After 60 minutes, bring the temperature of the mashing grain up to 170°F and hold for 10 minutes. This is our mash out.
- 5) Time to remove the grain. Lift the bag full of grain out of the brew pot. Let the liquid in the bag dribble into your wort. Once that is done, put the bag inside of a brewing pail, or another empty pot. There will be about 4 gallons of wort in the brew pot, we need to get it to 6 gallons before we can begin the next stage.
- 6) Run warm water through the grains in the bag, aim for 170°F – let it run through the grains and add to the brew pot. Add until you reach 6 gallons.
  - a. PSA: It is natural to think that the grains need to be squeezed to get all the liquid out of them, DO NOT DO THIS. Aggressively squeezing the grains will lead to tannin extraction and a doughy taste in your beer. Lightly pressing the bag is fine, but do not try to squeeze every last drop out.

Boiling -> Hop addition time

- 1) Bring 6 gallons of your wort to a rolling boil, and let it boil for 5 minutes, this is called the hot break.
- 2) Set a 60-minute timer. Keep the wort boiling (212°F) and uncovered.
- 3) With 45 minutes left in the timer, add ½ ounce of Magnum hops.
- 4) With 15 minutes left, add 1 tsp of Irish Moss, and if you're using a wort chiller add that too.
- 5) With 10 minutes left in the timer, add 1 ounce of Saaz hops to the boil.
- 6) With 5 minutes left in the timer, **add ¼ tsp of Yeast Lightning to the boil.**
- 7) When your timer goes off, turn off the heat, and then proceed to the cooling stage.
- 8) Now it's time to cool the beer down to 75°F (20-25°C) as quickly as possible.
  - a. We love using a wort chiller for this, it can get the beer down to temperature in 20-30 minutes. Otherwise, you can immerse the brew pot in an ice bath or wait it out. The longer it takes, the greater the risk of infection

Fermentation -> Turning the wort into beer

- 1) After the boil is done it is time to be extra careful regarding sanitation. We recommend using a no-rinse sanitizer called Starsan. Mix ¼ tsp of it with water in a 500ml spray bottle. Before we touch any part of the beer, we spray it with Starsan.
- 2) Transfer the cooled wort into your fermenting pail or carboy. Run it through a strainer to catch any hop or grain residue.
  - a. It is also an important time to take a hydrometer reading. It should be around 1.048 give or take a few points.
- 3) Your choice of fermentation vessel is important. During primary fermentation, it will bubble up quite a bit, you want to be sure there is airspace for it to work away. Otherwise, the pressure of it will push out the airlock.
- 4) Make sure the wort has been cooled to at least 25°C!!! Adding yeast at a higher temperature will likely kill it.
- 5) Once the beer is in the fermenter, pour in the entire package of Hefeweizen yeast from Escarpment Labs.
- 6) Put the bung and airlock in the hole (make sure there is water filled up to the line in the airlock). If using a pail, make sure the lid is sealed tight. Put the pail in a room that is in the range of 20-25°C.

- 7) Let the beer ferment for 10 days. It will do the majority of the fermentation in the first few days, but letting it sit will help with clarity and settling flavours.
- 8) It's now been 10 days; time to proceed to the bottling stage. First, take a hydrometer reading. It should be somewhere between 1.008-1.012
- 9) Lately, we have been of the opinion that secondary is an unnecessary step. Unless you are kegging, we recommend skipping secondary and going straight to the bottling process. Clarification can occur in the bottle rather than in a carboy, and the risk of oxidization is greatly reduced.

## Bottling -> We're getting close to Beer Time now.

- 1) Rack the now fermented beer into a bucket.
- 2) At the same time, mix the priming sugar with 300ml of boiling water and add to the beer. Stir it in VERY gently.
  - a. Make sure to check out a priming calculator to verify the correct amount of sugar. Too much sugar and your beer will end up foamy, or even start blowing the caps off! Too little and the beer won't be fully carbonated.
- 3) Rack the beer into your bottles or growlers. Then, let them sit for 2-3 weeks at room temperature. Chill and enjoy!