

# Am I Right Ladies?

Hazy Wheat IPA – 5.5 Gal - OG 1.060 – FG 1.014 – ABV 5.9% - IBU 25 – SRM 4.5

*The hazier the better, am I right, ladies?* Behold -- Dana's first recipe!

Dana joined our team in 2020 as a student and amateur stand-up comedian who loved cider and whiskey, but not beer -- while she still enjoys those things (probably too much, am I right, ladies?), she has grown to enjoy beer as well, especially sours and other juicy brews.

This is the first beer that Dana has ever developed, and like last month's Jean Claude Van Darn Good Belgian Ale, the Am I Right, Ladies? began with a name and resulted in a delicious BOTM. This phrase is something she says a lot on stage while "performing" her "comedy," and while it's mostly said to ease the tension of a joke that may have landed poorly, this Hazy Wheat IPA with an ABV of 5.9% will likely do the same if you drink enough of it! As a nod to her budding (read: fruitless) career in comedy, we've used Escarpment Labs' Classic Wit liquid yeast for this recipe, and with Vic Secret hops at center stage, this brew bears a tropical and juicy punchline. Take the fruitiness one step further by adding 2oz of peach flavouring at the bottling and/or kegging stage. We're confident that this won't be a one-liner, am I right ladies?

## Ingredients

### Grains

	Amount (lbs)
Canadian 2 Row	3.0
Wheat Malt	6.0
Flaked Wheat	2.0
Golden Naked Oats	1.0
Chit Malt	1.0
Acidulated Malt	0.1

### Hops

	Amount (oz)
El Dorado	1
Vic Secret	1
Vic Secret	2
Vic Secret	2

### Hop Schedule

FLAME OUT  
FLAME OUT  
FLAME OUT – Add at 180°F  
DRY Hop – 6 Days into Fermentation

### Yeast

Weizen 1 – Escarpment Labs 1 Package

### Extras – Sold Separately

\*Calcium Chloride 1 tsp at mash in.

*Adds some of that lovely haze to the beer*

\*Peach Flavouring 2oz at bottling/kegging

*PURELY optional. Adds a peach flavour which melds nicely with the hops.*

DME/Dextrose 150g (1/2 cup) at bottling for priming

[Step by step Instructions on the other side](#) →→→

## Important Tips on Brewing

- Be extra cautious when it comes to cleaning! Once you have stopped boiling your wort everything that gets in contact with the beer **MUST** be sanitary.
- The temperature of your mash is **ABSOLUTELY CRITICAL**. Not being in the 150-155f range can drastically affect your beer. Make sure you correct the temperature ASAP once all the grain has been added to the mash.
- Always let your beer ferment for 10 days! Do not disturb it, do not open the lid. It is absolutely natural for the airlock to stop bubbling after a few days, it is still fermenting though.
- Oxidization: Airspace is always something to consider. When undergoing primary fermentation airspace is needed so that the beer can bubble up and ferment vigoursley without leaking out of the container. The fermentation creates a layer of CO2 that remains in the pail due to the airlock. Once primary fermentation is over, and the lid has been opened, the layer of CO2 dissipates, and oxygen replaces it. At this point airspace can ruin your beer. When racking into carboys make sure they are filled to the top, or you blast CO2 inside to prevent oxidization. Ask us for details on this!
- Before bottling, make sure you use a priming calculator (many can be found online) to verify the amount of sugar that needs to be added.

## Instructions

Mashing -> converting the grain into a fermentable liquid.

- 1) Bring 6 gallons of water in your brew pot to 155°F. This is our strike temperature. Turn off the heat to the pot.
- 2) If you are using standard Guelph tap water, add 1 tsp of **Calcium Chloride** to the water. *This raises the calcium in the water which brings out the hazy look we're going for.*
- 3) Wrap the muslin/nylon bag around the brew pot and slowly pour all the milled grains into the bag. Stir them in while adding to prevent clumps. The addition of grain should drop the temperature down to 150-155°F.
- 4) We want to mash the grain at 154°F for 60 minutes. It is very important to hold the temperature at 152°F. If the temperature rises above 155°F it hurts the fermentation, or if it dips below 149°F it can lead to a thinner tasting beer.
  - a. The first 15-30 minutes are essential for the success of your brew. The temperature HAS TO BE IN THE RANGE OF 150-155°F. Sometimes adding the grain to the strike water does not lower the temperature enough, in this case add a little bit of cold water to bring the temperature down. Cover the pot with your lid and let it sit.
  - b. Most brew pots will be able to maintain 152°F without adding heat for 20 minutes, we recommend checking the temperature every 15 minutes, and if it drops add more heat to bring it up. We recommend opening the lid and using a thermometer in the liquid.
- 5) After 60 mins, bring the temperature of the mashing grain up to 170°F & hold for 10 minutes. This is our mash out.
- 6) Time to remove the grain. Lift the bag full of grain out of the brew pot. Let the liquid in the bag dribble into your wort. Once that is done, put the bag inside of a brewing pail, or another empty pot. There will be about 4 gallons of wort in the brew pot, we need to get it to 6 gallons before we can begin the next stage.
- 7) Run warm water through the grains in the bag, aim for 170°F – let it run through the grains and add to the brew pot. Add until you reach 6 gallons.
  - a. PSA: It is natural to think that the grains need to be squeezed to get all of the liquid out of them, **DO NOT DO THIS**. Aggressively squeezing the grains will lead to tannin extraction and a doughy taste in your beer. Lightly pressing the bag is fine, but do not try to squeeze every last drop out.

Boiling -> Sterilizing the wort time.

- 1) Bring 6 gallons of your wort to a rolling boil, and let it boil for 5 minutes, this is called the hot break. Start a 60-minute timer. Keep the wort boiling (212°F) and uncovered.
- 2) With 15 minutes left in the timer, if you have a wort chiller, we recommend adding it now, otherwise keep boiling.
- 3) When the timer finishes you will turn the heat off and add hops **Immediately**.

Cooling & Whirlpooling -> Let's Get Hoppy

- 1) When your timer goes off, turn off the heat, and immediately add 1 ounce of El Dorado & Vic Secret. Do not actively cool the wort. Let the wort sit for 10 minutes. After the 10 minutes are complete, begin cooling the beer down to 180F (*it is entirely possible that it may have cooled naturally to that level on its own*)

- 2) Once the wort is at 180°F add 2 ounces of Vic Secret and do not actively cool the beer for 10 minutes. Adding hops at 180°F will maximize the flavour of the hops but add just a little bitterness.
- 3) After the 10 minutes are complete. Start cooling the beer down to 25°C, this is our yeast pitching temperature.

## Fermentation -> Turning the wort into beer

- 1) After the boil is done it is time to be extra careful in regard to sanitation. We recommend using a no-rinse sanitizer called Starsan. Mix ¼ tsp of it with water in a 500ml spray bottle. **Before we touch any part of the beer, we spray it with Starsan.**
- 2) Transfer the cooled wort into your fermenting pail or carboy. Run it through a strainer to catch any hop or grain residue. With all of the hop matter in this beer, it might take a while to strain through all the hops.
  - a. It is also good time to take a hydrometer reading. It should be around 1.059 give or take a few points.
- 3) Be sure to use a pail for fermentation. It will be hard to rack a carboy with all the dry hops that are added.
- 4) Make sure the wort has been cooled to at least 25c!!! Adding yeast at a higher temperature will likely kill it.
- 5) Once the beer is in the fermenter, shake up and pour in the package of Weizen 1 yeast.
- 6) Put the bung and airlock in the hole (make sure there is water filled up to the line in the airlock). If using a pail, make sure the lid is sealed tight.
- 7) **Temperature for this yeast:** Weizen yeasts are very flexible with temperature requirements. Different temperatures will bring out different flavours in the finished beer. Cooler temps bring more clove esters, while warmer temps bring out more banana. For this recipe, we believe targeting banana esters is the preferred way. Which means we recommend fermenting the beer around 22-24°C, this yeast can be fermented between 18-24°C.
- 8) *Let the beer ferment undisturbed for 6-7 days before the next step. You will see a lot of activity In the first couple of days and then It will slow down - resist the temptation to remove the lid, let the beer do Its thing!*
- 9) After 6 to 7 days have passed, it is time to add the dry hops. Quickly open the lid or remove the bung and pour in 2 ounces of Vic Secret.
  - a. Potential oxidization is a concern here. If you have CO2 available, we recommend spraying a layer of it in the fermenter after adding the hops.
  - b. If you don't have CO2, then we recommend making a small tincture of dextrose and water. Boil 100ml in the kettle and mix with 100g of dextrose. Stir and dissolve, and then pour into the fermenter. This will create a mini fermentation which will result in the production of CO2 which keeps the oxygen at bay. Have the tincture ready before you add the hops. **The less time the lid/bung is open the better!**
- 10) Let the beer sit for 3 more days after adding the dry hops.
- 11) After 10 days have passed, take a hydrometer reading. It should be somewhere between 1.010-1.014.
- 12) Lately, we have been of the opinion that secondary is an unnecessary step. Unless you are kegging, we recommend proceeding to the bottling stage. Clarification can occur in the bottle rather than in a carboy, and the risk of oxidization is greatly reduced.

## Bottling -> We're getting close to Beer Time now.

- 1) Rack the now fermented beer into a bucket.
- 2) At the same time, mix the priming sugar with 300ml of boiling water and add to the beer. Stir it in VERY gently.
  - a. Make sure to check out a priming calculator to verify the correct amount of sugar. Too much sugar and your beer will end up foamy, or even start blowing the caps off! Too little and the beer won't be fully carbonated.
  - b. **Peach Flavouring:** If you are wanting to add the peach flavouring, now is the time to add 2 ounces of that into the bottling bucket (or keg).
- 3) Rack the beer into your bottles or growlers. Then, let them sit for 2-3 weeks at room temperature. Chill and enjoy!