



WOOBLES
TINY CAKE

PATTERN

CAKE

With pink and white yarn.

Rnd 1. (pink yarn) start 7 sc in a magic loop (7)

To keep track of where you are, use a stitch marker to mark the beginning of each round, move the stitch marker to the first stitch of that round.

Rnd 2. 7 inc (14)

Rnd 3. [sc, inc] x 7 (21)

Rnd 4. 21 sc blo (21)

Rnd 5. 21 sc (21)

Your piece might start curling - that's totally normal. For a neater final look, push the middle of your piece until it curves the other way. This makes the "right side" face out. Then keep crocheting to the left. If you're a lefty, keep crocheting to the right.

Rnd 6. (switch to white yarn) 21 sc (21)

Rnd 7. (switch to pink yarn) 21 sc (21)

Rnd 8. 21 sc (21)

Rnd 9. [sc blo, dec blo] x 7 (14)

Stuff the piece so that the top and bottom of the cake are flat.

Rnd 10. 7 dec (7)

Fasten off leaving a long tail. Thread a needle with the tail; then use it to pull the yarn tail through the front loops of each stitch. Pull tight to close the remaining gap and hide the tail.

FROSTING

With white yarn.

Top frosting

Step 1.

Sl st join the yarn in the last unworked front loop from round 4 of the cake. Insert the hook from the top to the bottom of the cake.

Step 2.

Ch 3, sl st in the same stitch as the sl st join.

Step 3.

[Ch 3, sl st in the next unworked front loop] x 19

Step 4.

Ch 3, sl st in the same stitch as the sl st join.

Step 5.

Fasten off and hide the yarn tail.



FLAME

With yellow yarn

Rnd 1. ch 5 (5)

Rnd 2. sl st, hdc, sc, sl st, ch 1. Rotate the piece to work on other side of the foundation chain. sl st, sc, hdc, sl st. sl st into the first stitch of round 2.

Fasten off leaving a long tail. Thread a needle with the tail; then use it to sew the flame to the center top of the cake.



Bottom frosting

Repeat steps 1-5 for the top frosting, but this time in the unworked front loops from round 9 of the cake.