



Assembly Line Scrapbooking

January 2018 Club Scrap® Deluxe Surprise

Materials:

- Surprise CS® Deluxe Kit

Tools and Supplies:

- 12" Paper Trimmer
- Adhesive
- Foam Adhesive
- Tape
- 3x14" CS® Grid Ruler
- Scissors
- Stapler and Staples
- CS® Bookbinding Glue
- CS® Ink Applicator
- CS® White Pigment Ink
- Craft Knife and Cutting Mat

LB = Left Base Page
RB = Right Base Page


Measurement Conversions:
 .125 = 1/8"
 .25 = 1/4"
 .5 = 1/2"
 .625 = 5/8"
 .75 = 3/4"

Preparation:

Trim the White printed cutaparts into sections as indicated by the artwork. While trimming the cutaparts and papers according to the instructions, distribute the pieces to a pile or file designated for each double page spread as referenced in the diagram. Trim the 1x12" printed red strip into two 1/2" pieces and use them plain side up and paired with washi tape on layouts 11 and 12.

If you do not have an item to complete the layout as shown, simply omit or substitute the item. Refer to [the blog](#) for more details about page assembly. (clubscrap.com/0118-layouts-cards)


12x12 White Cutapart




12x12 White Cutapart



12x12 Green Print




12x12 White Print




- Place one 12x12 Green Print right side up into the trimmer; cut at 9 and 3". Trim the 6x12 horizontally at 8 and 4".
- Place one 12x12 White Print into the trimmer with the glasses on the left; trim at 9.5 and 7". Rotate the 7x12 clockwise and cut horizontally at 7.25". Cut the 2.5x12 strip without the word "cheers" horizontally at 10, 7.5, 5 and 2.5".

12x12 Black Plain




12x12 Green Plain




- Trim one 12x12 Black Plain at 11, 10, 8.25, 7.625, 7, 5.5 and 4". Cut the 4x12 horizontally at 6".
- Cut one 12x12 Green Plain at 11.25, 10.5 and 6". Trim the 6x12 horizontally at 8 and 4". Cut the 4.5x12 horizontally at 9.25 and 6.5". Trim each 2.75x4.5 horizontally at 2.25".




8½x11 Blue Plain



8½x11 Blue Plain




8½x11 White Print




- Trim one 8.5x11 Blue Plain vertically at 5". Cut the 5x11 horizontally at 10.5, 7 and 3.5". Trim the 3.5x11 horizontally at 10.5, 7 and 3.5".
- Cut one 8.5x11 Blue Plain horizontally at 9.25 and 6.25". Trim the 6.25x8.5 horizontally at 4.25". Cut the 3x8.5 horizontally at 7.25, 6 and 3".
- Place one 8.5x11 White Print horizontally into the trimmer with the balloons on the top; trim at 4.5".


8½x11 White Print



8½x11 Pink Plain




8½x11 Pink Plain



- Place one 8.5x11 White Print vertically into the trimmer with the balloons on the left; trim at 5.5". Place the 3x11 horizontally into the trimmer with the text upside down; cut at 9".
- Cut one 8.5x11 Pink Plain vertically at 4.25". Trim each 4.25x11 horizontally at 5.5".
- Trim one 8.5x11 Pink Plain horizontally at 10.75 and 6.25". Cut the 6.25x8.5 horizontally at 4.25". Trim one 4.25x6.25 horizontally at 6". Cut the 4.5x8.5 horizontally at 6.5". Trim the 2x4.5 horizontally at 4 and 2".




8½x11 Red Print



11. Trim one 8.5x11 Red Print horizontally at 5.5”.

Layouts 1 & 2



- 12x12 White Print (LB)
- 12x12 Black Plain (RB)
- 8.5x11 Red Print (not cut)
- (2) 4.25x6.25 Red Photo Mats
- (2) 4.25x6.25 Blue Photo Mats
- (2) 4x6 Green Plains
- 1.75x8.5 Blue Plain
- White Cutaparts
- Blue Satin Ribbon
- Washi Tape



Layouts 3 & 4



- (2) 12x12 Pink Plains (LB & RB)
- (2) 3x12 Green Prints
- (3) 4x6 Green Prints
- 2x2.5 White Print
- 2.25x2.75 Green Plain
- 6.5x8.5 White Print
- 4.5x8.5 White Print
- White Cutaparts
- Washi Tape
- Glitter Flakes
- Pink Ribbon
- Pink Fabric Covered Button

Layouts 5 & 6



- (2) 12x12 Red Plains (LB & RB)
- 4.25x6.25 Blue Photo Mat
- 4.75x7 White Print
- 7x7.25 White Print
- 2.5x2.5 White Print
- 2.5x12 White Print
- 1.5x12 Black Plain
- 1x12 Black Plain
- 4x6 Green Plain
- (3) 3.5x3.5 Blue Plains
- 1.25x3 Blue Plain
- 3x3 Blue Plain
- White Cutaparts
- Stencil
- Green, Blue, and Red Fabric Covered Buttons
- Silver Wish Charm




Layouts 7 & 8



- (2) 12x12 Pink Prints (LB & RB)
- (3) 4.25x6.25 Black Photo Mats
- (3) 2.5x2.5 White Prints
- (2) .625x12 Black Plains
- 1.75x12 Black Plain
- White Cutaparts
- Pink Ribbon
- Black Ribbon
- Glitter Flakes


Layouts 9 & 10



- 12x12 Green Print (LB)
- 12x12 Green Plain (RB)
- 1x12 Black Plain
- 1.5x12 Black Plain
- (3) 3.5x5 Blue Plains
- (2) 4.25x6.25 Blue Plains
- 3x3 Blue Plain
- 1.25x3 Blue Plain
- (2) 4.25x5.5 Pink Plains
- White Cutaparts
- Washi Tape
- Pink Ribbon
- Silver "Wish" Charm




Layouts 11 & 12



- (2) 12x12 Black Prints (LB & RB)
- (2) 4.25x6.25 Green Photo Mats
- 4.25x6.25 Red Photo Mat
- 4.5x6.5 Green Plain
- (3) 2.25x2.75 Green Plains
- (2) .75x12 Green Plains
- (2) .5x12 White Cutaparts (Plain Side Up)
- (2) 5.5x8.5 Red Prints
- White Cutaparts
- (4) Fabric Covered Buttons
- Green Satin Ribbon
- Washi Tape

Layouts 13 & 14



- (2) 12x12 Blue Plains (LB & RB)
- 4.25x6.25 Green Photo Mat
- (2) 4x6 Black Plains
- 2x3 White Print
- 3x9 White Print
- 5.5x11 White Print
- (2) 4.25x5.5 Pink Plains
- 4.25x6.25 Pink Plain
- 4.25x6 Pink Plain
- 4.5x6.5 Pink Plain
- (2) 2x2 Pink Plains
- White Cutaparts
- Green Satin Ribbon

