

BERNAT® VELVET CABLE CROCHET BLANKET



CROCHET | SKILL LEVEL: **INTERMEDIATE**

ABBREVIATIONS

Approx = Approximately

Beg = Beginning

Ch = Chain(s)

Dcbp = Yoh and draw up a loop around post of next stitch at back of work, inserting hook from right to left. (Yoh and draw through 2 loops on hook) twice.

Dcfp = Yoh and draw up a loop around post of next stitch at front of work, inserting hook from right to left. (Yoh and draw through 2 loops on hook) twice.

Hdc = Half double crochet

Pat = Pattern

Rep = Repeat

St(s) = Stitch(es)

Trfp = (Yoh) twice and draw up a loop around post of next stitch at front of work, inserting hook from right to left. (Yoh and draw through 2 loops on hook) 3 times.

WS = Wrong side

Yoh = Yarn over hook

MEASUREMENTS

Approx 48" x 60" [122 x 152.5 cm], excluding tassels.

GAUGE

12 hdc and 9 rows = 4" [10 cm].

INSTRUCTIONS

Notes:

- Pat worked over foundation ch multiple of 10 ch +6.
- Ch 2 at beg of row **does not** count as hdc.

Ch 146. See chart on page 2.

1st row: (WS). 1 hdc in 3rd ch from hook. 1 hdc in each ch to end of chain. Turn. 144 hdc.

2nd row: Ch 2. 1 hdc in each of first 4 hdc. *Skip next 3 sts. (1 trfp around next st) 3 times. *Working* in front of sts just worked, 1 trfp around each of 3 skipped sts. 1 hdc in each of next 4 hdc. Rep from * across. Turn.

3rd row: Ch 2. 1 hdc in each of first 4 hdc. *(1 dcbp around next st) 6 times. 1 hdc in each of next 4 hdc. Rep from * across. Turn.

MATERIALS

Bernat® Velvet™ (10.5 oz/300 g; 315 yds/288 m)

Smokey Violet (32016)

9 balls

Size U.S. I/9 (5.5 mm) crochet hook **or size needed to obtain gauge.**
5" [12.5 cm] wide piece of cardboard for tassels.

BERNAT® VELVET CABLE CROCHET BLANKET

4th row: Ch 2. 1 hdc in each of first 4 hdc. *(1 dcfp around next st) 6 times. 1 hdc in each of next 4 hdc. Rep from * across. Turn.



5th row: As 3rd row.

Rep 2nd to 5th rows for pat until work from beg measures approx 60" [152.5 cm], ending on a 3rd row.






Fasten off.

FINISHING

Loopy Tassels (make 28): Wind yarn around a piece of cardboard 5" [12.5 cm] wide 15 times. Tie through loops securely at 1 end. Wrap yarn 3 times around Tassel 1" [2.5 cm] down from tied end. Fasten securely. **Do not** cut loops at bottom of tassels. Sew 1 Tassel centered on each cable at top and bottom edges of Blanket (as shown in photo).



STITCH KEY

-  = chain (ch)
-  = half double crochet (hdc)
-  = front post double crochet (dcfp)
-  = back post double crochet (dcbp)
-  = front post treble crochet (trfp)

