



MATERIALS

Red Heart® Super Saver® Ombre™ (10 oz/283 g; 482 yds/440 m)

Contrast A Jazzy (3966) **2 balls or 791 yds/723m**

Contrast B Scuba (3961) **2 balls or 833 yds/762 m**

Size U.S. 8 (5 mm) Susan Bates® circular knitting needle 29" [74 cm] long **or size needed to obtain gauge.** Susan Bates® stitch markers. Susan Bates® yarn needle. 4" [10 cm] wide piece of cardboard for tassels.



KNIT | SKILL LEVEL: EASY

ABBREVIATIONS

Approx = Approximate(ly)

Beg = Begin(ning)

K = Knit

Kfb = Increase 1 stitch by knitting into front and back of next stitch

K2tog = Knit next 2 stitches together

Rem = Remaining

Rep = Repeat

RS = Right side

Ssk = Slip next 2 stitches knitwise one at a time. Pass them back onto left-hand needle, then knit through back loops together.

St(s) = Stitch(es)

Tog = Together

WS = Wrong side

MEASUREMENT

Approx 42" [107 cm] square.

GAUGES

15 sts and 28 rows = 4" [10 cm] in garter st.

INSTRUCTIONS

Note: This Blanket is worked in four Squares from corner to corner.

SQUARES

Make 2 in A and 2 in B.

Cast on 2 sts. Working back and forth across needle in rows, proceed as follows:

1st row: (RS). (Kfb) twice. 4 sts.

2nd row: Knit.

3rd row: K1. Kfb. Knit to last 2 sts. Kfb. K1.

Rep last 2 rows until piece measures 19" [48 cm] wide across side edge, ending on a WS row.

Beg Decreasing: Next row: (RS). K1. K2tog. Knit to last 3 sts. ssk. K1.

Next row: Knit.

Rep last 2 rows until there are 6 sts rem.

Next row: K1. (K2tog) twice. K1. 4 sts.

Next row: K4.

Next row: (K2tog) twice. 2 sts.

Cast off.

FINISHING

Sew 4 Squares together as shown in photo.

Edging: First Side: With RS facing and A, pick up and knit 140 sts evenly across side edge of Blanket. Knit 2 rows.

Cast off knitwise (WS).

Second, Third and Fourth Sides:

With RS facing and A, pick up and knit 142 sts evenly across side edge of Blanket (including side of previous edging). Knit 2 rows.

Cast off knitwise (WS).

Tassel: (make 4 with B)

Cut a piece of cardboard 4" [10 cm] wide. Wind B around cardboard 50 times. Break yarn, leaving a long end and thread end through a needle. Slip needle through all loops and tie tightly. Remove cardboard and wind yarn tightly around loops ½" [1.5 cm] below fold. Fasten securely. Cut through rem loops and trim ends evenly. Sew 1 Tassel to each outer corner of Blanket.

