

# Cozy Cable Wrap

Level: Intermediate

#### SIZE

One Size

#### **FINISHED MEASUREMENTS**

Width: 24"

Length: 64" (not including fringe)

#### **MATERIALS**

Premier® Yarns Serenity® Chunky (100% Acrylic; 3.5 oz/100 g, 109 yds/100 m)

• 700-41 Smoke – 7 balls

or

**Premier® Yarns** *Serenity® Chunky* (100% Acrylic; 10.5 oz/300 g, 328 yds/300 m)

• 1061-07 Smoke – 3 balls

Needles: US Size 11 (8 mm) straight needles

or size needed to obtain gauge

**Notions:** Tapestry needle, cable needle, crochet hook (optional for adding fringe)

#### **GAUGE**

11 sts x 15 rows = 4" in St st **Save time, check your gauge.** 

#### STITCH GUIDE

**Staghorn Cable Panel** (*20 sts*) **Row 1 (RS):** P2, k4, **2/2RC, 2/2LC**, k4, p2. **WS Rows 2, 4 and 6:** K2, p16, k2. **Row 3:** P2, k2, **2/2RC**, k4, **2/2LC**, k2, p2. **Row 5:** P2, **2/2RC**, k8, **2/2LC**, p2.
Rep Rows 1-6 for patt.

**Reverse Staghorn Cable Panel** (*20 sts*) **Row 1 (RS):** P2, **2/2LC**, k8, **2/2RC**, p2. **WS Rows 2, 4 and 6:** K2, p16, k2.

Row 3: P2, k2, 2/2LC, k4, 2/2RC, k2, p2.

**Row 5:** P2, k4, **2/2LC**, **2/2RC**, k4, p2.

Rep Rows 1-6 for patt.

**2/2RC (2/2 Right Cross):** Slip 2 sts onto cable needle and hold in back, k2, k2 from cable needle.

**2/2LC (2/2 Left Cross):** Slip 2 sts onto cable needle and hold in front, k2, k2 from cable needle.

#### **PATTERN NOTES**

This Wrap is worked flat from end to end with optional fringe added once the knitting is complete.

#### **WRAP**

Cast on 66 sts. Work 1" even in Garter st.

Setup Row 1 (RS): K2, work Staghorn Cable

Panel over 20 sts (beg with Row 1), k1, work

Reverse Staghorn Cable Panel over 20 sts, k1,
work Staghorn Cable Panel over 20 sts, k2.

Setup Row 2 (WS): K2, work Staghorn Cable

Panel over 20 sts, p1, work Reverse Staghorn

Cable Panel over 20 sts, p1, work Staghorn

Cable Panel over 20 sts, k2.

Cont in est'd patt until Wrap meas 63" from cast-on edge. Work 1" even in Garter st. Bind off all sts.

### Finishing Fringe

Cut 96 – 16" lengths of yarn. Holding 2 lengths together as one, fold in half forming a loop on one end. Insert crochet hook into end of Wrap from back to front pull the looped end of fringe partially through the edge. Pass the loose ends through the loop being sure to keep ends even. Pull taut. Place each group of fringe approximately 1" apart. Repeat for other end of Wrap. Weave in ends.

## Cozy Cables Wrap

project continued

### **Abbreviations**

beg begin(ning)cont continueest'd establishedGarter st Knit every row.

**k** knit

**meas** measures

p purlpattpatternRS right side

rep repeat(ing) st(s) stitch(es)

**St st** Stockinette stitch: knit on RS rows,

purl on WS rows.

**WS** wrong side



