

Adventures in Homebrewing - www.HomeBrewing.org 313 - 277 - 2739 (BREW)

Cinco de Mayo Especiale

ANAL RES	Light notes of caramel and toasted grains, finishes with Saaz for a spicy hop character.					Original Gravity: 1.050
						Final Gravity: 1.012
	Extract Recipe					Color SRM : 16.28
						Alcohol by Volume : 4.82
	read all the instructions before you begin brewing, to ensure you have all the ingredients and fully understand the process.					IBU: 33.24
Clean	It is important to thoroughly clean and sanitize all of your brewing equipment.					
Steep	Begin by heating 2.5 gallons of water in your brew pot. Add speciality grains and tie a knot at one end of the "Grain Bag" leaving room for the grains to be loose in the bag. Place the Grain Bag in the water. Slowly raise the temperature to 150° to 160°F (max temp.). Steep your grains at this temperature for 20 minutes. After 20 minutes, remove the "Grain Bag" from the pot. Do not squeeze the bag, just let the liquid drain from the bag into the pot. The water is now "Wort" at this point. Grains : 0.5 lbs Victory 0.5 lbs Victory 0.5 lbs Crystal Malt (120 °L+) 0.25 lbs Amber Malt					
Fermentables & Start of Boil - Begin 60 minutes of boiling	Bring the "Wort" to a boil. It should be a rolling boil, but be careful to avoid a "Boil Over". Once you achieved a boil, remove the brew pot from the heat source.					Fermentables :
						6 lbs Liquid Malt Extract Pale
	Stir the extracts, and fermentables into the wort until it has all dissolved. It is important to make sure none of the extracts or fermentables are sitting on the bottom of the brew pot, as it will scorch when returned to the heat source. Return the wort to a rolling boil and follow Hop Schedule :					
Hop & Additive						
Schedule Cooling the wort		Ounces	Hop/Additives	Hop Addition	Boil Time (minutes)	4
		,	4HBU and 3HBU pack	Boil/Bittering	60	-
	1 oz Saaz Aroma 5 Once the 60 minute boil is over, it is time to cool the wort. There are many ways to cool a wort, the				-	
and preparing the fermentor	chiller. Cool the wort to approximately 100° F as quickly as possible. The fermenting equipment needs to be sanitized. This can be done while the wort is cooling. Be sure to clean and sanitize the fermenters, airlock, lid, hose, hydrometer and test jar and rubber stopper. Anything that may come into contact with the wort should b sanitary. Transfer the wort into the primary fermenting vessel, then top off with cold water until a total of 5.125 gallons is in the primary fermenter back and forth once the lid is in place.					
Take the reading	This is the time th	hat you will wan	to take a specific gravity rea	ding. Use a hy	drometer and record the	e reading.
Pitch the yeast	Once the wort is cooled to 78° F, it is safe to pitch the yeast. Pitch according the proper procedures of the type of yeast you have. Seal the fermenter tight. Attach the sanitized airlock and stopper. Fill the airlock with water. Fermentation should begin within 24 - 48 hours. "Do Not Disturb' until fermentation is complete. During the fermentation process, CO2 will begin to escape the airlock. Follow manufacturer's pitch instructions and recommended temperature for fermentation. Suggested Yeast : White Labs 001 California A Yeast Yeast Fermentis Safale US-05					
Fermenting - Primary	Once the Primary fermentation is complete, approximately 1 to 2 weeks, rack the beer into the secondary fermenter.					
Fermenting - Secondary	If the recipe calls for Dry Hops or additives that need to go into the secondary, add these now. The Secondary Fermentation should be complete within 1 to 2 weeks.					
Bottling	Siphon finished beer into a bottling bucket. If the recipe calls for any Bottling Additives to be added to the bottling bucket, add them now.					
	At this point, follow bottling or kegging proceduresCheers!					
			555 P			

Adventures in Homebrewing - www.HomeBrewing.org 313 - 277 - 2739 (BREW)