



The Screaming Habdabs Wheat IPA



You ever have that unexplained twitchiness that begins with goose bumps on the back of your neck and then works its way like freaky fingers beneath your hairline and along your scalp and tickles your brain around the outermost periphery of your cerebral cortex until you're sure that the top of your head is going to explode with delight? If you've nodded yes to any part of this question, then undoubtedly you've taken a hearty swig of this scandalously unique IPA and have been struck by the SCREAMING HABDABS! For when you looked away during that briefest moment, we secretly replaced the barley malt in your wort with wheat, and now your taste buds are besieged with the bready zing and full-bodied goodness of a hop-bomb ale that fizzes your senses in turbulent deliciousness and all but guarantees that something you'd otherwise deem important within those precious confines of your brain will go POP!

Just the Facts, Ma'am:

BJCP Style: 14B. American IPA
Original Specific Gravity: 1.069 - 1.073
Final Specific Gravity: 1.010 - 1.014
Alcohol by Volume: 7.7%
Color: 9 SRM (A nerve-annihilating shade of amber!)
International Bittering Units: 65
Time to Awesome Drinkability: 6 Weeks!

(Okay, so it's wheat. Take it up with the BJCP, those pencil-necked, pencil pushing bureaucrats!)

Brewing Supplies & Flavors:

1 Small Muslin Bag
5 oz Priming Sugar

Pre-Brew Day Checklist:

If you are using liquid yeast, it is always desirable to make a yeast starter when fermenting higher alcohol brews. Making a yeast starter allows you to propagate to a greater (and necessary) cell count to ensure complete fermentation. You can find the complete yeast starter instructions at www.boomchugalug.com/yeaststarter.htm

Brew Day Checklist:

On brew day, you will require the following equipment:

- Brew Pot - A 5 gallon brew pot is ideal, but never use a pot that is less than 4 gallons.
- Long-handled spoon or paddle for stirring the boiling wort.
- Primary Fermenter - A 6½ gallon (or greater) food-grade plastic bucket with lid, or a 6½ glass carboy.
- Airlock
- Stopper (if using a carboy)
- Funnel (if using a carboy)
- Hydrometer (Optional, if you want to measure your specific gravity)
- Sanitizing Solution
- Scissors
- Siphon Setup

On the day you rack the beer into the secondary fermenter, you will require the following equipment:

- 5 gallon carboy
- Stopper
- Airlock
- Siphon Setup

The Magical Procedure:

Liquid Yeast Activation Before Brewing:

If you are fermenting with liquid yeast, you must activate the yeast packet before it is ready to pitch. Always check the manufacturing date stamped on the yeast packet. Yeast that is less than 1 month old may be activated on brew day. A yeast that is more than 2 months old may require additional preparation time. Always make sure your yeast has been properly activated before using. Please see www.boomchugalug.com/wyeast.htm for complete liquid yeast activation instructions.

Time to Brew!

Total Boiling Time: 65 Minutes. While your wort is boiling, you should sanitize your fermentation equipment, such as your primary fermenter, airlock, scissors, stopper, etc. After you have sanitized your fermenter, fill it with 2 gallons of cold water, into which you will later add your hot boiled wort. Also, before beginning this recipe,

Ingredients:

Fermentables:

Malt Bag 1

4 lbs. Wheat Malt Extract Syrup

Malt Bag 2

4 lbs. Wheat Malt Extract Syrup

1 lb Corn Sugar (Dextrose)

Grains & Wort Additives:

5 oz 10L Crystal Malt (Crushed)

5 oz Biscuit Malt (Crushed)

6 oz Torrified Wheat (Crushed)

Hops:

1 oz Horizon Hops (Bittering, 65 Minutes)

¼ oz Cascade Hops (Bittering, 65 Minutes)

¼ oz Centennial Hops (Bittering, 65 Minutes)

¼ oz Willamette Hops (Bittering, 65 Minutes)

¼ oz Zythos Hops (Bittering, 65 Minutes)

¼ oz Cascade Hops (Flavor, 5 Minutes)

¼ oz Centennial Hops (Flavor, 5 Minutes)

¼ oz Willamette Hops (Flavor, 5 Minutes)

¼ oz Zythos Hops (Flavor, 5 Minutes)

½ oz Cascade Hops (Flavor & Aroma, Dry Hop)

½ oz Centennial Hops (Flavor & Aroma, Dry Hop)

½ oz Willamette Hops (Flavor & Aroma, Dry Hop)

½ oz Zythos Hops (Flavor & Aroma, Dry Hop)

Yeast:

Liquid Yeast: Wyeast 1010 American Wheat or

Wyeast 1272 American II Yeast

Or

Dry Yeast: Safale US-05 Yeast

Flip the sheet to continue the magic. Also, this is a good time to pour a cold one! →





The Screaming Habdabs Wheat IPA



Page 2....Wow, this is good stuff. I wish there could be more!

divide out the required hop quantities for each scheduled addition. To measure ¼ oz of hops, simply divide each 1 oz bag into two equal halves. Then take half of the half. This accuracy is adequate for brewing this recipe.

1. Place the crushed grains in the muslin bag and add to 2 gallons of water. Measure the water volume carefully to ensure you extract the proper amount of hop bitterness during the boil.
2. Heat water until the temperature is between 150° and 170°F. Steep the grains between this temperature range for 30 minutes. Steeping longer than 30 minutes does not hurt.
3. Remove and discard the grains, and bring this mixture to a boil. Remove the pot from the heat and add **Malt Bag 1**. To prevent scorching, stir until all of the malt is dissolved. Then bring this mixture to a boil. Watch for boilovers!
4. When boiling begins again, add 1 oz of Horizon hops and ¼ oz each of Cascade, Centennial, Willamette and Zythos hops. Boil these hops for the entire 65 minutes.
5. With 5 minutes remaining in the 65 minute boil, pause the brew timer, remove the kettle from the heat, and add **Malt Bag 2** and the corn sugar. Stir until dissolved and bring the wort back to a boil.
6. When boiling begins again, add ¼ oz each of Cascade, Centennial, Willamette and Zythos hops. Boil for the last 5 minutes.

Chill out, Man! (Chill the Wort)

1. At the end of the 65 Minute boil, cool the wort to approximately 75°F as quickly as possible. With extract brewing, the easiest way to quick-chill the wort is to place your brew pot into a sink full of ice. For complete instructions using this method, please see www.boomchugalug.com/cooling.htm.
2. Add your chilled wort to the 2 gallons of water already in your fermenter.
3. Add any extra water needed to bring the total volume in your fermenter to 5 gallons.
4. If you would like to measure the specific gravity, now is a good time. To get an accurate reading, it is important to make sure all of the heavy wort extract you added to the fermenter has been completely mixed in the water.

Pitch the Yeast! (Into the Wort, But Not Out the Window!)

1. When your wort has cooled to 75°F (70° - 78°F is okay), aerate the wort before adding the yeast. Simply close the fermenter and swirl around to mix in oxygen. If you are swirling a carboy, it is helpful to place the carboy on a thick, folded blanket to avoid damaging the vessel.
2. After aerating, pitch (add) the yeast. Use the sanitized scissors to cut open the yeast packet. If you are using liquid yeast, sanitize the pack before opening. If you are using dried yeast, simply sprinkle the yeast over the wort. No mixing is necessary with dried yeast.
3. Close the fermenter, attach the airlock, and keep the fermenter warm (between 70° - 78°F) until you see fermentation beginning, such as the airlock bubbling once every 30 seconds. Wrapping the fermenter with a blanket is an easy way to keep the fermenter warm.

Primary Fermentation:

There are several ways to know when fermentation has begun. First, you will begin to see bubbling through the airlock. If you are using a carboy, then you will usually see the yeast begin to form a layer over the beer's surface.

1. Once fermentation begins, move the fermenter to a room with the proper temperature. The ideal temperature to ferment this beer is between 60° - 72°F. Do not let the temperature drop below 60°F. If you do, fermentation may stop too soon. That's a bummer, man.

2. Active fermentation may take as long as two weeks after pitching the yeast, although fermentation may finish in 3 to 5 days.

Secondary Fermentation:

After about one week, fermentation will begin to slow. This is a good time to siphon the beer into the 5 gallon glass carboy.

1. Dry hop: When siphoning your beer into the secondary, add the final ½ oz each of Cascade, Centennial, Willamette and Zythos hops. Just cut 'em open and dump 'em in. Dude, that was easy!
2. Allow the beer to rest in the secondary for 1 - 2 weeks before bottling.

Time to Bottle!

There are several ways to tell when fermentation is complete (besides your drooling). If you correctly pitched the yeast and fermentation quickly began, and if the beer fermented vigorously and the fermenter was always within the correct temperature range (60° - 72°F), then fermentation should finish in two weeks or less. You should see virtually no activity in the airlock. For example, if the airlock only bubbles once a minute or longer, then fermentation should be complete. If you are unsure if fermentation has ended, you may use your hydrometer to measure the specific gravity. If your specific gravity does not change after two or more days, then fermentation is complete and you are ready to bottle!

1. Before bottling, sanitize your bottling bucket, auto siphon (or racking cane), hose, bottle filler, caps and bottles. Glass bottles may be sanitized one day in advance by baking them in the oven. Instructions for bottle baking may be found at www.boomchugalug.com/baking_bottles.htm.
2. Dissolve 5 ounces (weight) or 3/4 cup of priming sugar (dextrose / corn sugar) in 16 oz water. Boil for 5 minutes.
3. Pour the sugar solution into the bottling bucket, and siphon in the beer. Siphon carefully, trying to minimize splashing and aeration of the beer. Also when siphoning, be sure to leave behind the sediment at the bottom of the fermenter. When done siphoning, gently stir the beer in the bucket to make sure all of the sugar solution has been dissolved. Your racking cane makes a convenient stirring wand.
4. Elevate your bottling bucket, and attach your siphon hose and bottle filler to the bucket's spigot. Fill the bottles to about 1 inch from the top, and cap each bottle.

Carbonation and Maturation!

Now that your bottles are primed and capped, the remaining yeast will undergo a second fermentation in the bottle whereby they eat the priming sugar and produce carbon dioxide, which is trapped in the bottle to produce the carbonation. While your beer is carbonating, it will also be clearing and maturing - the young, rough undeveloped flavors develop into your magical beverage! Your wondrous elixir reaches awesome drinkability about 6 weeks from the day you began the brew, but don't be surprised if it keeps getting better as time goes on.

1. Place your bottles in a dark place at room temperature (62°F - 75°F), and wait at least two weeks for the beer to carbonate. It is important to keep the beer between 62°F - 75°F for carbonation to develop. If the beer cools below 62°F, it may not properly carbonate. In brewing, this is officially known as the buzzkill. Keep it warm, let it carbonate!
2. Once your beer is carbonated, you may store it in a cool place. Unfiltered home-brew is unfiltered, and unfiltered beers will improve with time. If your young beer is rough or yeasty, these flavors will mellow over time. Cheers!

