Yarnspirations™

spark *your* inspiration!

Version 1

Version 2

NEW FORMAT

O'Go™ Tangle-Free · Quick-Start

SUPER BULKY 6 · 🧶 CROCHET | SKILL LEVEL: **EASY**

ABBREVIATIONS

Approx = Approximately
Beg = Beginning
Ch = Chain(s)
Pat = Pattern
Rem = Remaining
Rnd(s) = Round(s)
Rep = Repeat

RS = Right side
Sc = Single crochet
Sc2tog = Draw up a loop in each of next 2 stitches. Yoh and draw through all loops on hook.
Sl st = Slip stitch

St(s) = Stitch(es)
Tog = Together
WS = Wrong side
Yoh = Yarn over hook

MATERIALS

Bernat® Blanket™ O'Go™ (10.5 oz/300 g; 220 yds/201 m)

Version 1 Agave (42010)	1 O'Go
Version 2 Fired Clay (42008)	1 O'Go

Agave — C, A, B

Fired Clay — C, A, B

Size U.S. J/10 (6 mm) crochet hook **or size needed to obtain gauge.** Fiberfill stuffing. Yarn needle.

MEASUREMENT

Approx 7¾" [19.5 cm] diameter.

GAUGE

10 sc and 9 rows = 4" [10 cm].

INSTRUCTIONS

Note: Pattern starts with circle for Ball Top. Each Panel is then worked in rows beg with 2 sts from Ball Top. Panels are then sewn tog with mattress st. Ball Bottom is closed off with circle to close gap at bottom of Panels.

Ball Top: With C, ch 2.
1st rnd: 6 sc in 2nd ch from hook. **Do not** join. 6 sc.
2nd rnd: 2 sc in each sc around. Join with sl st to first sc. 12 sc. **Do not** fasten off.

Proceed in rows as follows:
First Panel:
**1st row: (RS). Ch 1. 1 sc in each of first 2 sc. Turn. 2 sc.
2nd row: Ch 1. 2 sc in first sc. 1 sc in next sc. Turn. 3 sc.
3rd row: Ch 1. 1 sc in first sc. 2 sc in next sc. 1 sc in last sc. Turn. 4 sc.
4th row: Ch 1. 1 sc in first sc. 2 sc in next sc. 1 sc in each of last 2 sc. Turn. 5 sc.
5th row: Ch 1. 1 sc in each of first 2 sc. 2 sc in next sc. 1 sc in each of last 2 sc. Turn. 6 sc.
6th row: Ch 1. 1 sc in each of first 3 sc. 2 sc in next sc. 1 sc in each of last 2 sc. Turn. 7 sc.
7th row: Ch 1. 1 sc in each of first 3 sc. 2 sc in next sc. 1 sc in each of last 3 sc. Turn. 8 sc.
8th row: Ch 1. 1 sc in each of first 4 sc. 2 sc in next sc. 1 sc in each of last 3 sc. Turn. 9 sc.
9th row: Ch 1. 1 sc in each of first 4 sc. 2 sc in next sc. 1 sc in each of last 4 sc. Turn. 10 sc.

10th to 12th rows: Ch 1. 1 sc in each sc to end of row. Turn.
13th row: Ch 1. 1 sc in each of first 4 sc. Sc2tog. 1 sc in each of last 4 sc. Turn. 9 sc.
14th row: Ch 1. 1 sc in each of first 3 sc. Sc2tog. 1 sc in each of last 4 sc. Turn. 8 sc.
15th row: Ch 1. 1 sc in each of first 3 sc. Sc2tog. 1 sc in each of last 3 sc. Turn. 7 sc.
16th row: Ch 1. 1 sc in each of first 2 sc. Sc2tog. 1 sc in each of last 3 sc. Turn. 6 sc.
17th row: Ch 1. 1 sc in each of first 2 sc. Sc2tog. 1 sc in each of last 2 sc. Turn. 5 sc.
18th row: Ch 1. 1 sc in first sc. Sc2tog. 1 sc in each of last 2 sc. Turn. 4 sc.
19th row: Ch 1. 1 sc in first sc. Sc2tog. 1 sc in last sc. Turn. 3 sc.
20th row: Ch 1. 1 sc in first sc. Sc2tog. 2 sc. Fasten off.**

Second Panel: With RS facing, join B with sl st to next sc of Ball Top. Work from ** to ** as given for First Panel.

Third Panel: With C, work as given for Second Panel.

Fourth Panel: With A, work as given for Second Panel.

Fifth Panel: With C, work as given for Second Panel.

Sixth Panel: Join A with sl st to next sc of Ball Top.
Work from ** to ** as given for First Panel working in Stripe Pat:
With A, work 2 rows.
With B, work 2 rows.
These 4 rows form Stripe Pat.

FINISHING
With RS facing and using coordinating worsted weight yarn, join Panels using mattress st. Before joining last 2 Panels, stuff firmly (See Diagram on page 3).


MATTRESS ST

Ball Bottom:
With RS facing, join C with sl st to bottom of a Panel.
1st rnd: Ch 1. Work sc evenly around, working 2 sc into bottom of each Panel. **Do not** join. 12 sc.
**2nd rnd:** *Sc2tog. Rep from * around. Join with sl st to first sc. 6 sc.
Fasten off, leaving long end. Draw end tightly through rem sts and fasten securely.

For accessibility support, please contact customer care at 1-888-368-8401 or access@yarnspirations.com.

CROCHET BEACH BALL TOY 2 of 3

Version 1

1. Panels worked from Ball Top

6th | 5th | 4th | 3rd | 2nd | 1st

2. Panel sides joined with mattress st

3. Panel ends joined with Ball Bottom

Version 2

6th | 5th | 4th | 3rd | 2nd | 1st

For accessibility support, please contact customer care at 1-888-368-8401 or access@yarnspirations.com.

CROCHET BEACH BALL TOY   **3 of 3**