



@PlantMagicPlus
 PlantMagicPlus
 PlantMagic_Plus
 www.plant-magic.co.uk

Coco Schedule

Grow

	Start/Rooting (3-5 days)	Week 1	Week 2
pH	5.7-6.4		
Coco Grow	EC: 0.8 1-3ml per L	EC: 1.0 1-3ml per L	EC: 1.2 1-3ml per L
Granules	Use 1 tablespoon per 10 litre of growing medium, spread evenly around potting hole for maximum root contact.		
Veg Boost	After potting-on with Granules water-in with Veg Boost at 1.5ml per litre.		
Enzyme		2ml per L	2ml per L
Root Stimulant	2.5ml per L	5ml per L	5ml per L
Evolution	Spray once per week until run-off.		
Hydro Silicon		0.5ml per L	0.5ml per L
Bugicide	Spray until run-off when infestation occurs.		

These are guidelines only, individual situations may vary.



@PlantMagicPlus
 PlantMagicPlus
 PlantMagic_Plus
 www.plant-magic.co.uk

Coco Schedule

Bloom

	Week 1	Week 2	Week 3	Week 4	Week 5	Week 6	Week 7	Week 8	Week 9
pH	5.7-6.4								
Coco Grow	EC: 1.2 2-3ml per L								
Coco Bloom		EC: 1.4 3-5ml per L	EC: 1.6 3-5ml per L	EC: 1.8 3-5ml per L	EC: 1.8 3-5ml per L	EC: 1.8 3-5ml per L	EC: 1.8 3-5ml per L	EC: 1.8 3-5ml per L	EC: 1.8 3-5ml per L
Ignition	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L
Enzyme	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L	2ml per L
Root Stimulant	5ml per L	5ml per L							
Biowetter	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L
Evolution	Spray once per week								
Bloom Boost				1ml per L	1.5ml per L	2ml per L	2ml per L	2ml per L	
Platinum PK 9-18				0.25ml per L	0.3ml per L	0.4ml per L	0.5ml per L	0.5ml per L	
Organic PK 4-8				1ml per L	1.5ml per L	2ml per L	2ml per L	2ml per L	
Boosting Powder				1x sachet per 100L	1x sachet per 100L	1x sachet per 100L	2x sachets per 100L	2x sachets per 100L	
Magne-Cal+	0.5ml per L	0.5ml per L	0.5ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	
Hydro Silicon	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	1ml per L	
Flush									5ml per L
Bugicide	Spray until run-off when infestation occurs.								

These are guidelines only, individual situations may vary. *Do not use Organic PK 4-8 in automated systems.

Made in UK