



WHEN USING CANNA COCO PROFESSIONAL PLUS GROWING MEDIA

WEEKS	-6	-5	-4	-3	-2	-1	1	2	3	4	5	6	7	8	FINAL WEEK	
GROWTH STAGE	CUTTINGS / SEEDLINGS		VEGETATIVE GROWTH				FLOWERING / FRUITING GROWTH									
CANNA VEGA START	20-30ml	20-30ml														
CANNA COCO A&B			10-15ml	15-20ml	20-25ml	20-25ml	25-30ml	25-35ml	30-35ml	30-35ml	35-40ml	20-25ml	20-25ml	20-25ml		
RHIZOTONIC	40ml	40ml	20ml	10ml	10ml	10ml	5ml	5ml	5ml							
CANNAZYM			25ml	25ml	25ml	25ml	25ml	25ml	25ml	25ml	25ml	25ml	25ml	25-50ml	25-50ml	
CANNA PK 13/14											15ml					
CANNA BOOST ACCELERATOR							20ml	20-40ml	20-40ml	20-40ml	20-40ml	20-40ml	20-40ml	20-40ml		
CANNA FLUSH															20 ml	
TARGET CONDUCTIVITY	6-8	6-8	6-8	8-10	10-12	10-12	12-15	12-16	15-16	15-16	16-18	10-14	10-14	10-14		

All applications are based on dilution in 10L of water unless otherwise stated

Conductivity readings are for nutrients and additives only. Add your tap water reading onto these guidelines

TIPS ON USING CANNA COCO

- The above feeding schedule should be used as a guide only. You should look for signals from your plant as to whether more or less feed is required. Environmental conditions such as temperature and humidity should also be taken into consideration.
- Canna Coco Professional Plus growing media has no nutrients in it. Before planting into the coco, water it with a nutrient solution containing 20-30ml per 10L of Canna Coco A&B with 40ml per 10L of Canna Rhizotonic. Ensure you get some run-off, around 5-10%. This will pre-soak the Coco to enable good establishment.
- Your nutrient solution pH should be between 5.5 and 6.5. 5.8 - the ideal is 6.2. Make sure you check your pH after adding your nutrients and additives and adjust if necessary.
- When watering coco it's important to get run-off. Around 20-30% is ideal. Do not let this run-off get sucked back up into the pots.