

is ready for use

Substrate types
Coco coir, coco blends, perlite, peat, soil
System
Drain-to-waste, recirculating

Natural, clean, easy to follow nutrition for high value crops



	Growth phase Week of growth	Vegetative Week 1	WEEK	Vegetative Week 2·3·4>	WEEK	Flower Week 1	WEEK	Flower Week 2	WEEK	Flower Week 3	WEEK	Flower Week 4	WEEK	Flower Week 5	WEEK	Flower Week 6	WEEK	Flower Week 7	WEEK	Flower Week 8	WEEK	Final Flower Week
1	Fill tank with fresh water	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water	S) PER	Refresh Water
2	FASILITOR - mix well -	<b>0.15</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	<b>0.3</b> ml/L	2 DAY(	<b>0.3</b> ml/L	2 DAY(	<b>0.3</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	<b>0.15</b> ml/L	2 DAY(	
3	MASSBOOST - mix well -	0.25 ml/L	-OR 1-	<b>0.25</b> ml/L	-0R1-	<b>0.33</b> ml/L	-OR 1-	<b>0.33</b> ml/L	-OR 1 -	<b>0.33</b> ml/L	-OR 1-	<b>0.33</b> ml/L	-OR 1 -	<b>0.33</b> ml/L	-0R1-	<b>0.33</b> ml/L	-0R1-	<b>0.33</b> ml/L	-0R 1-	0.25 ml/L	-OR 1 -	
4	PEAKBOOST - mix well -		PER 1L F		PER 1L F	<b>0.12</b> ml/L	PER 1L F	<b>0.14</b> ml/L	PER 1L F	<b>0.16</b> ml/L	PER 1L F	<b>0.12</b> ml/L	PER 1L F									
5	STARTBOOST - mix well -	0.25 ml/L	0.5 ml l	<b>0.25</b> ml/L	0.5 ml l	<b>0.5</b> ml/L	0.5 ml l		0.5 ml l		0.5 ml		0.5 ml I		0.5 ml l							
6	FINALEBOOST - mix well -		EN AT		EN AT		EN AT	<b>0.13</b> ml/L	EN AT	<b>0.17</b> ml/L	EN AT	0.25 ml/L	EN AT	<b>0.33</b> ml/L	EN AT	<b>0.4</b> ml/L	EN AT	<b>0.5</b> ml/L	EN AT	<b>0.67</b> ml/L	EN AT	
7	BLOOMBOOST - mix well -		D ECOZ		D ECOZ		D ECOZ	<b>0.2</b> ml/L	D ECOZ	<b>0.25</b> ml/L	D ECOZ	0.29 ml/L	D ECOZ	<b>0.33</b> ml/L	D ECOZ	<b>0.33</b> ml/L	D ECOZ	<b>0.4</b> ml/L	D ECOZ	<b>0.5</b> ml/L	D ECOZ	
8	BASE - mix well -	<b>1.25</b> ml/L	IER AN	<b>1.5</b> ml/L	ER AN		IER AN		IER AN		IER AN		IER AN		IER AN		FER AN		IER AN		IER AN	
	BASE to EC level		WA		WAT	1.2 - 1.4	WA	1.2 - 1.4	WA	1.2 - 1.4	WA	1.4 - 1.6	WA	1.4 - 1.6	WA	1.4 - 1.6	WA	1.2 - 1.4	WA	1.0 - 1.2	WA	
9	ECOZEN - mix well -		H WITH	0.25 ml/L	H WITH	<b>0.25</b> ml/L	н МІТН	<b>0.25</b> ml/L	н МІТН	0.25 ml/L	H WITH	0.25 ml/L	н МІТН	0.25 ml/L	н МІТН	0.25 ml/L	H WITH	<b>0.25</b> ml/L	H WITH	0.25 ml/L	н мітн	<b>0.5</b> ml/L
10	Check pH	рН 5.8	FLUS	рН 5.8	FLUSI	рН 5.9	FLUS	рН 6.0	FLUSI	рн 6.0	FLUS	рн 6.1	FLUS	рн 6.1	FLUS	рн 6.2	FLUS	рН 6.2	FLUSI	рн 6.2	FLUSI	рН 6.2
	Ni state and activ																					

PREMIUM QUALITY.
SUPERIOR FLAVOUR.



Connect with us
























## During **FLOWERING** growth phase





aptusplanttechaus **f** 

COST PER RUN



TANK MAINTENANCE

1 - 3 DAYS

As with any organic products, this program should not be used in DWC,

## **The APTUS Premium Program**

This program is the absolute gold standard of quality, flavour, oil production and shelf life.

This is the program for the grower looking to produce the absolute best flower they can or any extraction artists looking to increase the quality, colour and yield of their extracts.

It's recommended to mix fresh feed daily, bi-daily or every 3 days at a maximum to reduce the build-up of biofilm in tanks and irrigation systems. Fresh is best!

NFT or aeroponic systems. We also

and slabs. Cultivators running these

do not recommend this program

for rockwool or stonewool blocks

systems and substrates should

follow our CLEAN program.

aptusplanttechaus 👩