

GROW HEAVY

PROFESSIONAL GRADE

YEARS OF SCIENTIFIC RESEARCH, COMMERCIAL AGRICULTURAL PRODUCTION, AND PROVEN INDOOR FARMING EXPERIENCE GO INTO EVERY BATCH OF HEAVY 16. HEAVY 16 IS POWERFUL AND STRAIGHT FORWARD. NO GIMMICKS. NO NONSENSE. OUR BASIC FEED SCHEDULE IS A DIRECT AND EFFECTIVE SOLUTION FOR GARDENERS DEMANDING A SIMPLE, YET POTENT, NUTRIENT SYSTEM. USE OUR EXPERT FEEDING SCHEDULES FEATURED ONLINE TO UNLEASH YOUR GARDEN'S FULL POTENTIAL.

ARTISAN QUALITY

WE TAKE PRIDE IN MICROBREWING EVERY BATCH OF HEAVY 16. WE PRECISELY REFINE EACH INGREDIENT TO ENSURE CONSISTENCY AND PURITY BEFORE ANYTHING REACHES A BOTTLE. WE SOURCE OUR DERIVATIVES FROM TRUSTED PARTNERS AND NEVER SKIMP ON QUALITY. THIS EXTRA WORK IS WORTH IT TO US. WE WOULDN'T HAVE IT ANY OTHER WAY.



HEAVY 16 

	590	700	882	1050	1160	1260	1372	1470	1580	1580	1092	280	
	WEEK 1	WEEK 2	WEEK 3	WEEK 4	WEEK 1	WEEK 2	WEEK 3	WEEK 4	WEEK 5	WEEK 6	WEEK 7	WEEK 8	
VEG A	4 mL	5 mL	6 mL	7 mL									22 mL
VEG B	4 mL	5 mL	6 mL	7 mL									22 mL
BUD A					7.5 mL	8 mL	9 mL	9.5 mL	10 mL	10 mL	6 mL		60 mL
BUD B					7.5 mL	8 mL	9 mL	9.5 mL	10 mL	10 mL	6 mL		60 mL
ROOTS	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL	1 mL		11 mL
PRIME**	1 mL	1 mL	2 mL	2 mL	3 mL	3 mL	3 mL	3 mL	3 mL	3 mL	3 mL	2 mL	29 mL
FIRE				0.5 mL	0.5 mL	1 mL	1 mL	1.5 mL	2 mL	2 mL	1.5 mL		10 mL
FINISH	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	2.5 mL	10 mL	37.5 mL

MIXING PROCEDURE:

1. FILL RESERVOIR HALF WAY WITH FRESH FILTERED WATER.
2. ADD THE ADDITIVES (PRIME, ROOTS, FIRE, & FINISH) ONE AT A TIME DEPENDING ON DOSAGE.
3. SHAKE PART A WELL, MEASURE PROPER AMOUNT AND ADD TO RESERVOIR. WASH MEASURING CUP.
4. SHAKE PART B WELL, MEASURE PROPER AMOUNT AND ADD TO RESERVOIR. WASH MEASURING CUP.
5. AGITATE RESERVOIR, FINISH FILLING RESERVOIR, THEN MEASURE PPMS & ADJUST IF NECESSARY WITH (BASE A+B).
6. MEASURE & ADJUST PH TO ENSURE PROPER RANGES
(FOR HYDROPONIC MEDIUMS - HYDROTON, ROCKWOOL, COCO BETWEEN 5.5 - 6.2) (SOILS BETWEEN 6.2 - 6.8)
7. WATER IS READY FOR IRRIGATION.

* 700 CONVERSION FACTOR USED

** NEW PRIME CONCENTRATE DOSAGES

1. FOLIAR NOT INCLUDED ON CHART. SHOULD BE SPRAYED ON PLANTS AS BOTTLE RECOMMENDS.
2. ALL DOSAGE VALUES ARE mL/GAL
3. CAN BE USED FOR HYDRO, SOIL OR DWC. IT'S OUR LIGHTEST SCHEDULE FOR MORE ADVANCED REGIMENS VISIT - WWW.HEAVY16.COM/CALC.PHP

