

---

## Instructions / Windows 10 / English

1. If you need help at any time then please email [bob@iso2disk.com](mailto:bob@iso2disk.com)
2. Back up all data and photos that are important to you.
3. Ensure the disk or USB is ready in the computer when powered down.
4. You now need to bring up the boot menu.
5. Power up your computer and keep pressing the "boot key" at the same time.
6. The "boot key" is F12 for Dell, F9 for HP and sometimes F2 for other makes.
7. You should get the "boot menu" on the screen.
8. Select the Disk or USB and press "return" to start the installation.
9. You may see a message "press any key to boot from DVD", if so, immediately press a key.
10. Select "64 bit" or "32 bit" if you see this option. If not, just wait.
11. You need to wait a while for the next screen to appear.
12. Select country settings and click "next".
13. Click "install now" for a fresh installation.
14. There is a "repair" option at this stage which can be used to attempt a repair.
15. Click "I don't have a product key". This can be added once the install has finished.
16. Choose the version you wish to load ( Home or Pro).
17. Accept the license terms.
18. Click on "Custom (Advanced)".
19. You can attempt an "upgrade" at this stage. This will save all your files and applications.
20. Click "Drive Options" (advanced).
21. Click on partitions in turn and delete all.
22. When this is done you will end up with just one line (disk 0 unallocated space).
23. You will see a yellow "new" icon (do not click on this).
24. Click "next" - Do not click on "new".
25. Windows 10 will now start to load (this can take around 30 minutes).
26. Choose your region.
27. Click on Keyboard region.
28. Skip second keyboard option.
29. Click on "I don't have internet" (this can be added later).
30. Click "continue with limited set up".
31. Input a user name. You can leave password blank.
32. Say "no" and "deny" all options (these can be changed later).
33. Click on "Not Now" for Cortana.
34. Continue until complete.
35. Once complete you can add your Wifi details.
36. When done take out your disk or USB.
37. It is best now to delete all start up programs so you have a clean screen with no pop ups.
38. Press at the same time the keys "Ctrl", "Alt" and "Del"/"Delete" and a menu will appear.
39. Click on "Task Manager".
40. In the bottom left corner, click on "More Details".
41. Click on "Start Up" in menu bar at the top.
42. Click on those that are "Enabled" and disable them by clicking on "Disable" in the bottom right.
43. Restart and you are all done.
44. You can now perform "updates" which will perform all updates and add any drivers which may be missing.

### Activation, Microsoft Office and Windows 11 options

- 1 You will need to activated Windows 10. If you have a key you can enter it to activate.
- 2 If you do not have a key or it doesn't work, you can contact [bob@iso2disk.com](mailto:bob@iso2disk.com) to receive some advice as to where to purchase one. Keys can be purchased from internet sellers for around £10 or less.