eMeetLink User Manual

EMEET SmartCam C970/C970L

Device settings

Firstly, connect the device to the computer via USB cable. Open the eMeetLink software and enter the setting interface.

1. Firmware update

In the upper right corner, you can see your device's firmware version. Also, you can click the "update" button to get the latest version.



2. Camera settings

(1) Auto Privacy Protection

C970/C970L has an electronic privacy cover to protect personal privacy.

The auto privacy protection mode will be activated while you put the lens back to the stand facing upwards. Simply pull up the lens from the stand to recover shooting and audio in 3 seconds.

You can check the "Auto Privacy Protection" switch to open this function. When unchecked, the electronic privacy cover will be disabled.



(2) Image Flip

The image of this device supports flip horizontal or vertical. Check the "Flip Horizontal" button to validate the horizontal flip of the image. Check the "Flip Vertical" button to validate the vertical flip of the image.

Image flip

Horizontal flip	
Vertical flip	

3. Video settings

(1) Filters

There are four filters mode for your choices: Default, Customize, Black and White, or Cartoons. You can select according to your needs.

Default: In this mode, the other parameters such as brightness, contrast, sharpness, saturation, and white balance can not be adjusted.

Black and White: In this mode, the image will be black and white.

Cartoons: In this mode, you will get the image with a cartoon filter.

Customize: In this mode, you can drag the slider to adjust the image parameters like brightness, contrast, sharpness, saturation, and white balance according to your needs.

Video Filters ① Default BlackWhite Cartoon stomizati Anti-flicker 50Hz 60Hz Brightness 44% Contrast 47% Sharpness 35% Saturation 54% White Balance 39% C) **Restore defaults**

(2) Anti-flicker

Most countries use 50HZ as the power grid operating frequency, and some countries such as the United States use 60HZ.

Choose a suitable power frequency to avoid the screen flashing.



(3) White Balance

In the customize mode, you can click the "Auto" button to open or close the white balance auto adjustment function.

When the auto button shows blue, the white balance of the image will be adjusted automatically.

When the auto button shows grey, you can adjust the white balance according to your needs.



(4) Restore Default Settings

After restoring default settings, all operating settings will be restored to the factory mode.

\$			- 🗆 ×
۲		Vertical flip	
		Video	
		Filters ①	
		Default BlackWhi	te Cartoon
		stomizati	
		Anti-flicker	
		50Hz 60Hz	
	Are you sure to restore the default	Brightness	
	Settings?	— •	44%
		Contrast	
	Cancel Confirm		47%
		Sharpness	
			35%
		Saturation	
			54%
		White Balance	Auto
			39%
	C970	Restore del	aults

Settings

In this setting interface, you can change the language according to your need. Check your eMeetLink software version and update it.

Set up	
Co Language selection	English
Software update	
Software Version	
Detect new version	Check for upo
Software update notification	
Auto update	
O Notification	
Allow popup	

Support

1. Feedback

Write your feedback here to get EMEET customer service support.



2. FAQs

There are some common questions for your reference.

					- 0
Feedback	FAQs	User Manual	Compatible device	Contact	
1. The device is	plugged int	to the USB port of the	computer, but the device is	not detected.	
Please unplug	the device US	SB and re-plug the cor	nputer USB port.		
2. Computer (F	C) software	cannot be updated.			
Please check if the official EME	the software ET website.	has already been the	latest version. You can also un	install the software and download the	latest eMeetLink software
3. After renam	ing the devi	ce, the updated device	e name is not displayed.		
Click [Save] and	[Confirm] th	ne device name.			
4. eMeetLink is	unavailable				
Please check if	your device i	s connected to the co	mputer via USB.		

3. User manual

Click the device to enter EMEET official website and get the user manual.



4. Compatible device

									-	
Feedback	FAQs	User Manual	Compatible	device	Contact					
🙁 camera										
		0	-	P			-			
Capsule	C950	C955	C960	C965	C970	C970L	C980 Pro			
0		5								
C990	Jupiter	Nova								
Microphor	ne									
	0		0		0					
M0	M2	M220	M2 Max	Luna	Luna Lite					
Earphone										
Q										
HS100										
Accessory										
eMute	A300	A200								

5. Contact info

