


T-APEX Software and App Upgrade Instructions

APP Upgrade


1. Connect the Tablet to a Computer

- Plug your tablet into a computer using a USB cable. You will see a device named "iPlay50" on your computer.




2. Transfer the APK File

- Copy the APP APK file to the root directory of the "iPlay50" device.




3. Install the App

- On the tablet, navigate to the "Files" app.
- Locate and select the APP APK file.
- Follow the prompts to install the APP.



4. Confirmation


- Once the installation is complete, the APP will be ready to use.



Software OTA (Over-the-Air) Update


1. Connect the Tablet to a Computer

- Connect your tablet to a computer using a USB cable. The device named "iPlay50" will appear on your computer.



2. Transfer the Software File

- Copy the software update file to the appropriate directory within the "iPlay50" device.




3. Power On and Open the APP

- Power on the T-APEX device.
- Open the installed APP on the tablet.

4. Connect the APP with T-APEX

- Navigate to Setting > Bluetooth on the tablet.
- Connect the APP to the T-APEX device via Bluetooth(RE07_XXXX).




5. Access the Version Menu

- Go to Setting > Version in the APP.
- Verify that the device version is displayed.




6. Start the OTA Update

- Press the OTA button.
- Enter the Admin Password: 7777.



7. Update Process

- The device will begin updating the package. During this process, "E2" will be displayed on the device.
- Wait for a beep sound from the device, indicating that the update is complete and the device will power off.



8. Verification

- Power on the device again.
- Re-enter the Version menu in the APP to check the updated device version.

