

Materials:

5 Different Fat Quarters:


- Cut (2) 9" x 12" for main body pieces from 2 different FQ
- Cut (3) 9" x 10" for pockets from 3 different FQ
- Cut (1) 4" x 10" for handle
- Cut (3) 2 1/2" x 20" strips for binding

Heavy Interfacing/Craftex (1) 9" x 12" pieces


Shape Flex/Lightweight Interfacing: (3) 9" x 10" pieces

Sewing Instructions:

Adhere the 2 main body pieces to either side of the heavy interfacing. Adhere the 3 different pocket pieces to each lightweight interfacing pieces. Fold each pocket piece in half with the interfacing on the inside so it measures 9" x 5". Layer the top pocket on the main body unit, 4" up from the bottom. Sew at 1/4" seam allowance. Layer the second pocket 2" up from the bottom and sew at 1/4" seam allowance. Place the 3rd pocket flush with the bottom edge of the main unit. Baste the sides of the unit in place.



Create the handle by pressing the 4" x 10" piece in half lengthwise. Open up and fold the raw edges towards the center crease. Fold in half again at the original crease, enclosing the raw edges. Top stitch the edges closed and a matching stitch along the opposite side. Fold the strap in half and place it at the top of the pocket unit, in the center on the back side. Stitch in place a few times for strength.



Binding: Using a traditional quilt binding, sew the strips together and press in half length-wise. Beginning along the side of the pocket unit, attach the binding to the backside, going over the handle (make sure the handle is flush with the back of the unit).

