

Bell's 2 Hearted Clone

Our tribute to a Bell's original. Grapefruit and pine throughout.
Refreshingly clean and easy to drink.

Original Gravity : 1.067

Final Gravity : 1.017

Color SRM : 8.74

Alcohol by Volume : 6.49

Procedure : Please read all the instructions before you begin brewing, to ensure you have all the ingredients and fully understand the process. It is important to thoroughly clean and sanitize all of your brewing equipment.

IBU : 70.00

Clean	It is important to thoroughly clean and sanitize all of your brewing equipment.	
Steep	Begin by heating 2.5 gallons of water in your brew pot. Add speciality grains and tie a knot at one end of the "Grain Bag" leaving room for the grains to be loose in the bag. Place the Grain Bag in the water. Slowly raise the temperature to 150° to 160°F (max temp.). Steep your grains at this temperature for 20 minutes. After 20 minutes, remove the "Grain Bag" from the pot. Do not squeeze the bag, just let the liquid drain from the bag into the pot. The water is now "Wort" at this point.	1 lb crystal malt (10 °L)
Fermentables & Start of Boil - Begin 60 minutes of boiling	Bring the "Wort" to a boil. It should be a rolling boil, but be careful to avoid a "Boil Over". Once you achieved a boil, remove the brew pot from the heat source. It is time to add : Stir the extracts, and fermentables into the wort until it has all dissolved. It is important to make sure none of the extracts or fermentables are sitting on the bottom of the brew pot, as it will scorch when returned to the heat source. Return the wort to a rolling boil :	8 lb liquid malt extract pale 1 oz Centennial
Boil - time for flavor hops and additives	After 45 minutes of boiling, add :	1 oz Centennial
Boil - time for aroma hops	After 55 minutes of boiling, add :	1 oz Centennial
Cooling the wort and preparing the fermentor	Once the 60 minute boil is over, it is time to cool the wort. There are many ways to cool a wort, the AIH recommendation is a wort chiller. Cool the wort to approximately 100° F as quickly as possible. The fermenting equipment needs to be sanitized. This can be done while the wort is cooling. Be sure to clean and sanitize the fermenters, airlock, lid, hose, hydrometer and test jar and rubber stopper. Anything that may come into contact with the wort should be sanitary. Transfer the wort into the primary fermenting vessel, then top off with cold water until a total of 5.125 gallons is in the primary fermenter. Aerate the wort at this point. This can be accomplished with an aeration stone or simply by rocking the fermenter back and forth once the lid is in place.	
Take the reading	This is the time that you will want to take a specific gravity reading. Use a hydrometer and record the reading.	
Pitch the yeast	Once the wort is cooled to 78° F, it is safe to pitch the yeast. Pitch according the proper procedures of the type of yeast you have. Seal the fermenter tight. Attach the sanitized airlock and stopper. Fill the airlock with water. Fermentation should begin within 24 - 48 hours. "Do Not Disturb" until fermentation is complete. During the fermentation process, CO2 will begin to escape the airlock. Follow manufacturer's pitch instructions and recommended temperature for fermentation. Suggested yeasts are :	White Labs 001 California Ale Yeast Wyeast 1056 American Ale Yeast Fermentis Safale US-05
Fermenting - Primary	Once the Primary fermentation is complete, approximately 1 to 2 weeks, rack the beer into the secondary fermenter.	
Fermenting - Secondary	The Secondary Fermentation should be complete within 1 to 2 weeks. Add the dry hops and secondary additives :	1 oz Centennial
Bottling	Siphon finished beer into a bottling bucket. If the recipe calls for any additives to be added to the bottling bucket, add them now. At this point, follow bottling or kegging procedures....Cheers!	