



Delirious Trembles Belgian Golden Strong Ale



The discombobulation begins with your first innocent sip, and suddenly that spasmodic twitch which begins at the corner of your mouth will spread like waves rippling through belly fat, and soon you'll be grinning like the Cheshire cat on laughing gas being tickled by a herd of pink elephants. Did you expect something different? Because in your chalice swirls an elegant elixir of exceptional character, with the lively effervescence twirling through that golden brew and anointing your tastebuds with a creamy mouthfeel of sweet malt, citrus fruits and a melange of interesting spice that ignites your senses like dancing alligators and delivers you to that psychedelic place of good taste, hysterical laughter and delirious trembles.

Just the Facts, Ma'am:

BJCP Style: 25C. Belgian Strong Golden Ale
Original Specific Gravity: 1.078 - 1.082
Final Specific Gravity: 1.012 - 1.016
Alcohol by Volume: 8.5%
Color: 6 SRM (Golden with Cold Sweats!)
International Bittering Units: 22
Time to Awesome Drinkability: 10 Weeks!

Your recipe kit includes the freshest malt, hops and yeast. If you are not going to brew your recipe immediately, it is important to refrigerate your yeast and hops. If your recipe includes bags of malt syrup, these should be refrigerated too. Bags of dried malt do not require refrigeration. Also, all grains are best stored at dry room temperature.

Ingredients:

Fermentables:

8.8 lbs Pilsen Light Malt Extract Syrup
2 lbs Light Candy Sugar

Hops:

1 oz Styrian Golding Hops (Bittering, 65 Minutes)
½ oz Saaz Hops Bittering, 65 Minutes)
½ oz Saaz Hops (Flavor & Aroma, 15 Minutes)

Yeast:

Liquid Yeast: Wyeast 1388 Belgian Strong Ale Yeast

Or

Dry Yeast: Mangrove Jack's M31 Belgian Tripel Ale Yeast OR
LaBrew® Abbaye Belgian Ale Yeast

AND Safale S-04 Dried Ale Yeast

Brewing Supplies & Flavors:

12 grams Coriander Seed (Ground, 10 Minutes)
4 grams Grains of Paradise (Ground, 10 Minutes)
½ tsp. Dried Ginger (10 Minutes)
5 oz Priming Sugar

Brew Day Checklist:

On brew day, you will require the following equipment:

- Brew Pot - A 5 gallon brew pot is ideal, but never use a pot that is less than 4 gallons.
- Long-handled spoon or paddle for stirring the boiling wort.
- Primary Fermenter - A 6½ gallon (or greater) food-grade plastic bucket with lid, or a 6½ glass carboy.
- Airlock
- Stopper (if using a carboy)

- Funnel (if using a carboy)
- Hydrometer (Optional, if you want to measure your specific gravity)
- Sanitizing Solution
- Scissors
- Siphon Setup
- Blow-Off Tube (Recommended)

If you choose to rack the beer into the secondary fermenter, you will require the following equipment:

- 5 gallon carboy
- Airlock
- Stopper

The Magical Procedure:

Liquid Yeast Activation Before Brewing:

If you are fermenting with liquid yeast, you must activate the yeast packet before it is ready to pitch. Always check the manufacturing date stamped on the yeast packet. Yeast that is less than 1 month old may be activated on brew day. A yeast that is more than 2 months old may require additional preparation time. Always make sure your yeast has been properly activated before using. For more information about yeast starters, please visit the 'Frequently Asked Questions' section on boomchugalug.com.

Time to Brew!

Total Boiling Time: 65 Minutes. While your wort is boiling, you should sanitize your fermentation equipment, such as your primary fermenter, airlock, scissors, stopper, etc. After you have sanitized your fermenter, fill it with 2 gallons of cold water, into which you will later add your hot boiled wort.

Note 1: This recipe has malt syrup additions at two different times during the boil. Please read all of the instructions before beginning.

Note 2: This recipe uses two different packs of yeast. Be sure to add both packs!

Note 3: Belgian yeast strains can ferment vigorously and foam out the top of the fermenter. We therefore recommend using a blow-off tube during the primary fermentation.

1. Add to 2½ gallons of water to your brew kettle, and bring this water to a boil. Measure this volume carefully to ensure you extract the proper amount of hop bitterness.
2. Add 4 cups of malt extract syrup (See Note 3 below). To prevent scorching, remove the pot from the heat when adding the syrup and stir until all of the malt is dissolved. Then bring this mixture to a boil. Watch for boilovers!

Note 3: Measuring 4 cups (32 fluid ounces) of malt syrup is easy! Make sure you use a measuring cup that holds at least 4 cups (32 fluid ounces). With scissors, cut off a SMALL corner of the malt syrup bag and then slowly squeeze the 4 cups of syrup into the measuring cup. If you are a little over or under, it's no problem. Before you add this malt syrup to your brew pot in Step 2, you may soften it by placing the measuring cup in the microwave and warming it for 30 seconds. Also, before Step 6, be sure to

Boomchugalug.com

Flip the sheet to continue the magic. Also, this is a good time to pour a cold one! →





Delirious Trembles Belgian Golden Strong Ale



Page 2....Wow, this is good stuff. I wish there could be more!

store the opened bag of syrup in an upright position (duh!). We find that propping it upright in a round plastic food storage container (like a Tupperware) to be the easiest.

3. When boiling begins, add 1 oz of Styrian Golding hops and ½ oz Saaz hops. Boil these hops for the entire 65 minutes.
4. With 15 minutes remaining in the 65 minute boil, add ½ oz Saaz hops.
5. With 10 minutes remaining in the 65 minute boil, add the spices (12 grams coriander, 4 grams grains of paradise & ½ tsp. dried ginger).
6. With 5 minutes remaining in the 65 minute boil, pause the brew timer and remove the kettle from the heat. Add the light candy sugar and the remaining malt extract syrup. Stir until dissolved, bring the wort back to a boil, and boil for the last 5 minutes.

Chill out, Man! (Chill the Wort)

1. At the end of the 65 minute boil, cool the wort to approximately 75°F as quickly as possible. With extract brewing, the easiest way to quick-chill the wort is to place your brew pot into a sink full of ice. For more information about cooling your wort quickly, please see 'Fast Wort Chilling' in the 'Frequently Asked Questions' section on our website.
2. Add your chilled wort to the 2 gallons of water already in your fermenter.
3. Add any extra water needed to bring the total volume in your fermenter to 5 gallons.
4. If you would like to measure the specific gravity, now is a good time. To get an accurate reading, it is important to make sure all of the heavy wort extract you added to the fermenter has been completely mixed in the water.

Pitch the Yeast! (Into the Wort, But Not Out the Window!)

1. When your wort has cooled to about 75°F (70° - 78°F is okay), aerate the wort before adding the yeast. Simply close the fermenter and swirl around to mix in oxygen. If you are swirling a carboy, it is helpful to place the carboy on a thick, folded blanket to avoid damaging the vessel.
Please note: This recipe uses two packets of yeast. The original liquid or dried strain of your choice plus the Safale S-04. This blend of two different strains of yeast contributes to its unique flavor.
2. After aerating, pitch (add) the yeast. Use the sanitized scissors to cut open the yeast packet. If you are using liquid yeast, sanitize the pack before opening. If you are using dried yeast, simply sprinkle the yeast over the wort. No mixing is necessary with dried yeast.
3. Close the fermenter, attach the airlock, and keep the fermenter warm (between 70° - 78°F) until you see fermentation beginning, such as the airlock bubbling once every 30 seconds. Wrapping the fermenter with a blanket is an easy way to keep the fermenter warm.

Primary Fermentation:

There are several ways to know when fermentation has begun. First, you will begin to see bubbling through the airlock. If you are using a carboy, then you will usually see the yeast begin to form a layer over the beer's surface.

1. Once fermentation begins, move the fermenter to a room with the proper temperature. The ideal temperature to ferment this beer is between 64° - 75°F. Do not let the temperature drop below the minimum specified temperature. If you do, fermentation may stop too soon. That's a bummer, man.
2. Active fermentation may take as long as two weeks after pitching the yeast, although fermentation may finish in 3 to 5 days.

Secondary Fermentation:

After about one week, fermentation will begin to slow. This is a good time to siphon the beer into the 5 gallon glass carboy. Allow the beer to rest in the secondary fermenter for about 2 weeks before bottling the beer.

Note: if your brewing equipment does not include a 5 gallon carboy (secondary fermenter), then allow the beer to age for about 2 more weeks in the primary fermenter before bottling the beer.

Time to Bottle!

There a several ways to tell when fermentation is complete (besides your drooling). If you correctly pitched the yeast and fermentation quickly began, and if the beer fermented vigorously and the fermenter was always within the correct temperature range (64° - 75°F), then fermentation should finish in two weeks or less. You should see virtually no activity in the airlock. For example, if the airlock only bubbles once a minute or longer, then fermentation should be complete. If you are unsure if fermentation has ended, you may use your hydrometer to measure the specific gravity. If your specific gravity does not change after two or more days, then fermentation is complete and you are ready to bottle!

1. Before bottling, sanitize your bottling bucket, auto siphon (or racking cane), hose, bottle filler, caps and bottles. Glass bottles may be sanitized one day in advance by baking them in the oven. More information about baking your bottles can be found under 'Baking Beer Bottles' in the 'Frequently Asked Questions' section on our website.
2. Dissolve 5 ounces (weight) or 3/4 cup of priming sugar (dextrose / corn sugar) in 16 oz water. Boil for 5 minutes.
3. Pour the sugar solution into the bottling bucket, and siphon in the beer. Siphon carefully, trying to minimize splashing and aeration of the beer. Also when siphoning, be sure to leave behind the sediment at the bottom of the fermenter. When done siphoning, gently stir the beer in the bucket to make sure all of the sugar solution has been dissolved. Your racking cane makes a convenient stirring wand.
4. Elevate your bottling bucket, and attach your siphon hose and bottle filler to the bucket's spigot. Fill the bottles to about 1 inch from the top, and cap each bottle.

Carbonation and Maturation!

Now that your bottles are primed and capped, the remaining yeast will undergo a second fermentation in the bottle whereby they eat the priming sugar and produce carbon dioxide, which is trapped in the bottle to produce the carbonation. While your beer is carbonating, it will also be clearing and maturing - the young, rough undeveloped flavors develop into your magical beverage! Your wondrous elixir reaches awesome drinkability about 10 weeks from the day you began the brew, but don't be surprised if it keeps getting better as time goes on.

1. Place your bottles in a dark place at room temperature (65 °F - 80 °F), and wait at least two weeks for the beer to carbonate. It is important that you keep the beer between 65 °F - 80 F° for carbonation to develop. If the beer cools below 65 °F, it may not properly carbonate. In brewing, this is officially known as the buzzkill. Keep it warm, let it carbonate!
2. Get your bottle opener handy dude (or dudette), because it's time to drink a beer! When pouring the beer into your glass, be sure to leave the bottle's sediment behind. That sediment is the yeast which carbonated your beer, and if you pour it into your glass, you'll make the beer cloudy and taste yeasty.
3. Once your beer is carbonated, you may store it in a cool place. Keep in mind that home-brewed is unfiltered, and unfiltered beers actually continue to improve with time. If your beer seems rough-around-the edges or tastes yeasty, these qualities usually morph into a smooth, clean beer over time. Cheers!

