



| | | | |
|-------------|------------|------------|------------------------------|
| O.G. | ABV | IBU | BREW TIME: 6 WEEKS |
| 1.046 | 4.7% | 9.4 | Primary: 2 Weeks |
| | | | Secondary: 2 Weeks |
| | | | Bottle Conditioning: 2 Weeks |

RASPBERRY WHEAT

Meet the Raspberry Wheat: Mild, approachable, and fruity, we've found this to be a good "gateway beer" as well as a nice end to a warm summer evening or dense chocolate cake. Medium-bodied with the flavor profile of a Bavarian Hefeweizen, but laced with tart, fruity raspberry aroma and flavor. Natural raspberry extract added to taste at bottling lets you tone down the fruit or turn it way up, as you prefer.

KIT INVENTORY

MALT EXTRACTS

6.3 lbs Wheat malt syrup

PREMIUM HOPS

1 oz Hersbrucker 60 min

OTHER FLAVORINGS

Raspberry Extract

Add at Bottling or Keg

SUGGESTED YEAST

YEAST

DRY YEAST:

Fermentis Safale WB-06

Optimum Temp: 59°- 75°F

LIQUID YEAST OPTIONS:

Omega Yeast OYL-021 Hefeweizen Ale

Optimum temp: 64°- 75°F

Imperial Yeast G01 Stefon

Optimum temp: 63°- 73°F

Wyeast 3068 Weihenstephan Wheat

Optimum temp: 64°- 75°F

BEFORE BREW DAY

- Upon arrival, unpack kit.
- Read all instructions before starting.
- Be sure you have all items listed in the Kit Inventory.
- Refrigerate liquid yeast. Check package for manufacture recommendations for brew day.
- If making a yeast starter, we suggest 24-48 hrs.
- Contact us if you have any questions or concerns.

YOU WILL NEED

- Homebrewing equipment for brewing 5 gallon batches.
- Boiling kettle (at least 3.5 gallons capacity).
- Approx. 2 cases of 12 oz or 22 oz pry-off beer bottles.
- **Optional** - 5 gallon carboy, with bung and airlock, to use as secondary fermentor.

BREWING NOTES

KEY STATS

Brew Day Date: _____

Secondary: _____

Important Additions: _____

Bottling/Kegging: _____

Fermentation Temp: _____

Yeast Strain #: _____

Measured OG: _____ FG: _____

ON BREWING DAY

1. Heat 2.5 gal of water.
2. Bring to a boil. Remove the kettle from burner and stir in **6.3 lbs Wheat malt syrup**.
3. Return to boil. The mixture is now called "wort", the brewer's term for unfermented beer.
NOTE: Total boil time is 60 min.
- **Add 1 oz Hersbrucker hops** at the start of boil
Note: If you have extra hops, store them in the freezer or they can be discarded.
4. Cool wort. When 60-minute boil is finished, cool wort to approximately 65-70°F as rapidly as possible. Use a wort chiller, or put kettle in an ice bath in your sink.
5. Sanitize fermenting equipment and yeast pack. While wort cools, sanitize fermenting equipment (fermenter, lid or stopper, airlock, funnel, etc) along with yeast packs.
6. Fill primary fermenter with 2 gal cold water, then pour in cooled wort. Leave any thick sludge in bottom of kettle.
7. Add more cold water as needed to bring volume to 5 gal.
8. Aerate wort: Seal fermenter and rock back and forth to splash for a few mins, or use an aeration system and diffusion stone.
9. Measure wort's specific gravity with a hydrometer. Record.
10. Add yeast once temp. of the wort is 70°F or lower (not warm to the touch). Sanitize and open yeast pack. Carefully pour contents into primary fermenter.
11. Seal fermenter. Add approx. 1 tbsp of water to sanitized fermentation lock. Insert airlock into rubber stopper or lid. Seal fermenter.
12. Move fermenter to a warm, dark, quiet spot until fermentation begins.

PRIMARY FERMENTATION

13. **Within 48 hours Active fermentation begins.**
You'll see a cap of foam on the surface of the beer. Specific gravity as measured with a hydrometer will drop steadily. You may see bubbles in the fermentation lock. Determine optimum temp. for this beer based on the yeast you selected from above.
14. **Within 1-2 weeks Active fermentation ends.**
Proceed to next step when:
 - Cap of foam falls back into the beer.
 - Bubbling in airlock slows down or stops.
 - Specific gravity as measured with a hydrometer is stable.

SECONDARY FERMENTATION (OPTIONAL)

- NOTE:** You may skip transferring to a secondary fermenter and simply leave the beer in the primary fermenter.
15. Sanitize siphoning equipment, airlock, carboy bung or stopper. Siphon beer from primary fermenter into secondary.
 16. Allow beer to condition in secondary fermenter for 2 weeks before proceeding with the next step. Timing is now somewhat flexible.

BOTTLING DAY (ABOUT 4 WEEKS AFTER BREWING DAY)

17. Sanitize siphoning and bottling equipment.
18. Mix a priming solution (sugar dissolved in water; carbonates bottled beer). Use the following amounts, depending on which type of sugar you use:
 - Corn sugar (dextrose) 2/3 cup in 16oz water.
 - Table sugar (sucrose) 5/8 cup in 16oz water.Bring solution to a boil. Pour into bottling bucket.
19. Siphon beer into bottling bucket, add Raspberry Extract to taste, and mix with priming solution. Stir gently to mix - *do not splash*.
20. Fill and cap bottles.

CONDITIONING (ABOUT 6 WEEKS AFTER BREWING DAY)

21. Condition bottles at room temp. for 1-2 weeks. After this point, store bottles cool or cold.
22. Serving: Pour into a clean glass. Be careful to leave any sediment at the bottom of the bottle. Cheers!

WE'VE GOT YOUR BATCH

We're so confident in the quality of our beer kits, we'll replace any kit, anytime, no questions asked.

CONNECT TO OUR COMMUNITY

Snap and share your brew, we know you're proud.
#NorthernBrewer NorthernBrewer.com